



WAIKATO SDSS

DOCUMENTATION



research institute for knowledge systems

DRAFT

Content: RIKS BV

Layout: RIKS BV

Illustrations: RIKS BV

Published by: RIKS BV

© RIKS BV
(insert date)

This is a publication of the Research Institute for Knowledge Systems (RIKS BV),
Witmakersstraat 10, P.O. Box 463, 6200 AL Maastricht, The Netherlands,
<http://www.riks.nl>, e-mail: info@riks.nl, Tel. +31(0)433501750, Fax. +31(0)3501751.

Product information

TODO

Waikato SDSS documentation

© RIKS BV (December, 2008)

RIKS Team leader:

- Hedwig van Delden

Contributing researchers (in alphabetical order):

- Jelle Hurkens
- Yu-e Shi
- Jasper van Vliet
- Roel Vanhout

Research Institute for Knowledge Systems BV
P. O. Box 463
6200 AL Maastricht
The Netherlands
www.riks.nl



DRAFT

Contents

PREFACE	V
1. INTRODUCTION	3
2. USER MANUAL	5
2.1 Getting started	5
2.1.1 Installing WAIKATO SDSS : Hard- and software requirements.....	5
2.1.2 Installing WAIKATO SDSS : Installation procedure.....	6
2.1.3 WAIKATO SDSS directory structure	7
2.1.4 MAP COMPARISON KIT directory structure	9
2.1.5 Starting WAIKATO SDSS	9
2.1.6 Screen Layout.....	11
The Caption bar.....	11
The Menu bar	11
The Toolbar.....	12
The Status bar	12
2.1.7 System information.....	12
Index	13
Using Help	13
Licence.....	13
About.....	13
2.1.8 Closing WAIKATO SDSS	15
2.1.9 If you experience problems	15
2.2 Running simulations.....	15
2.2.1 Opening a simulation.....	15
Opening a simulation file.....	15
The main window	16
2.2.2 Editing Input and Displaying output.....	17
Map window	17
Customizing map output.....	21
Graphs	24
Single Value and time.....	25
Tables.....	26
Map file.....	26
2.2.3 Running a simulation.....	27
Init.....	27

Step	28
Run.....	28
Stop.....	28
Reset.....	28
Pauses.....	28
2.2.4 Saving simulation results	30
Save simulation.....	30
Save simulation as.....	31
Write to Excel	32
Log maps.....	36
Animate maps	38
2.2.5 Analysing results	39
2.3 Policy interface.....	40
2.3.1 Overview of the policy interface	40
Step 1: Setting up the drivers	41
Step 2: Creating integrated scenarios.....	41
Step 3: Running the simulation.....	42
Step 4: Visualising indicators	42
Step 5: Analysing results	42
2.3.2 Setting up the drivers	43
External factors	43
Policy measures	46
Summary	50
2.3.3 Creating integrated scenarios.....	50
2.3.4 Running a simulation.....	51
Saving output results.....	51
Running the simulation.....	52
2.3.5 Visualising indicators	52
2.3.6 Analysing results	54
Analysing spatial results	54
Summary	57
2.4 Modeller interface	58
2.4.1 Overview of the system diagram	58
2.4.2 Model Building Blocks (MBB)	59
2.4.3 Connectors and Connections	59
2.4.4 Dialog windows.....	59
2.4.5 Individual model components.....	60
Land use change model.....	60
Economic model	69
Demography model.....	76
2.5 The WAIKATO SDSS menu system	77

2.5.1	The File Menu	77
2.5.2	Simulation menu.....	78
2.5.3	Options menu.....	78
2.5.4	Window menu.....	79
2.5.5	Help menu.....	79
2.6	Appendix	81
3.	THE INTEGRATED MODEL.....	85
4.	MODEL BUILDING BLOCKS	87
5.	INDICATORS	89
	REFERENCES	91

DRAFT

Preface

TODO

DRAFT

DRAFT

1. Introduction

DRAFT

2. User Manual

This chapter describes the user manual of **WAIKATO SDSS**, a decision support system build with the **GEONAMICA®** SDSS application framework. The **WAIKATO SDSS** is developed for the Waikato region to support Environment Waikato's Long-term Council Community Planning Process.

This manual contains five sections:

Section 2.1 "Getting started" explains how to install **WAIKATO SDSS** on your computer and how to start the program. It also describes the main features of the graphical user interface.

Section 2.2 "Running simulations" contains a step-by-step description of how to run a simulation in **WAIKATO SDSS**.

Section 2.3 "Policy interface" describes the steps of how a policy user carries out an integrated impact assessment with the **WAIKATO SDSS** system.

Section 2.4 "Modeller interface" describes the interface for the modeller to access the underlying models and to update data and parameter settings through the system diagram in **WAIKATO SDSS**.

Section 2.5 "The **WAIKATO SDSS** menu system" offers a systematic description of each option in the menu system.

2.1 Getting started

This chapter explains how to install **WAIKATO SDSS** on your computer and how to start the program. It also describes the main features of the graphical user interface.

2.1.1 Installing **WAIKATO SDSS**: Hard- and software requirements

WAIKATO SDSS runs on personal computers equipped with modern Intel or Intel compatible processors. To use **WAIKATO SDSS**, your computer should have the following hardware components:

- At least 1GB of RAM
- A hard disk with at least 10GB free

To make full use of the application, you should have the following software packages installed on your computer:

- Microsoft® Excel (version 97 or later) (optional)

The **WAIKATO SDSS** is developed for Windows XP. If you experience problems by installing the **WAIKATO SDSS** on Windows vista, please can contact us (see section 2.1.9).

2.1.2 Installing WAIKATO SDSS: Installation procedure

The following is a step-by-step description of the installation of **WAIKATO SDSS**. The installation/uninstallation of **WAIKATO SDSS** follows the standards for Windows.

If you have a previous version of the **WAIKATO SDSS** software installed on your machine, you will be asked whether you want to uninstall it first. It is better to uninstall it. If you would want to keep it, make sure to put (this new version of) **WAIKATO SDSS** in a separate directory. During the installation you may encounter a message asking whether you want to keep or replace certain files. It is preferred to replace them for use with **WAIKATO SDSS**. Keeping the old files may cause malfunctioning of the software.

To Install WAIKATO SDSS:


1. Start Microsoft Windows XP.
2. Insert the **WAIKATO SDSS** CD-Rom into the drive.
3. Click the *Start* button in the Windows XP Task bar. Move the mouse pointer to the *Settings* command and select the *Control Panel* option. As a result the *Control Panel* window will open. Select *Add or Remove Programs* icon by double clicking it. Next click the *Add New Programs* and the *CD or Floppy* buttons in the *Add or Remove Programs* dialog window.
4. Next, the installation program will be started and will request you to click the *Next* button until (1) the program has selected your CD-drive as the installation medium, and (2) until it will have found the *Waikato SDSS_1.0.0_setup.exe* program for **WAIKATO SDSS** on the CD-Rom. If the installation program does not find the CD-drive or the *Setup.exe*, then press the *Browse* button, navigate to the right drive, and find the *Waikato SDSS_1.0.0_setup.exe* on the **WAIKATO SDSS** CD-Rom. The command line '(drive): *Waikato SDSS_1.0.0_setup.exe*' will appear in the edit field of the *Run Installation Program* dialog window. Press *Finish* to continue the installation.
5. The wizard is started. A dialog window is opened asking you where to install **WAIKATO SDSS**. You may accept the default path, which is 'C:\Program Files\Geonamica' or press the *Browse* button and define an alternative location.
6. To go on, press the *Next* button. Otherwise to cancel the installation process, press the *Cancel* button.
7. Next the installation program suggests adding **WAIKATO SDSS** to the new Program Group **GEONAMICA®**. You are free to create another Group or to choose an existing one from the list shown.
8. Next the installation program will ask you to choose the features of **WAIKATO SDSS** you want to install. Select the *Waikato SDSS* option and *Data* option.
9. From that moment the installation application is decompressing the necessary files and puts them in the directory structure of **WAIKATO SDSS**.
10. Once the installation on the hard disk is completed, the program creates a group named *Geonamica* under the *Start* button and *Programs* command. It contains an item labelled *Geonamica*. When you double click this item, **WAIKATO SDSS** will be started and the *About* window will open. Click the *OK* button to open the *Open* dialog window.
11. Follow the procedure outlined in the steps 1 to 9 to install the **MAP COMPARISON KIT** and **OVERLAY-TOOL**. The files relative to the former are stored in the directory Map Comparison Kit and the files for the latter are stored in the directory Overlay Tool on the **WAIKATO SDSS** CD-Rom.
12. You can start to use the **WAIKATO SDSS** when the installation is finished (see section 2.1.5).

To Uninstall WAIKATO SDSS:


1. Click the *Start* button in the Windows XP Task bar. Move the mouse pointer to the *Settings* command and select the *Control Panel* option. As a result the *Control Panel* window will open. Select *Add or Remove Programs* icon by double clicking it. Next click the *Change or Remove Programs* button in the *Add or Remove Programs Properties* dialog window.
2. Next select **WAIKATO SDSS** from the list of applications that can be automatically removed by Windows and press the *Change/Remove* button.
3. The *Confirm File Deletion* dialog window will open. Press the *OK* button to confirm that you want to remove **WAIKATO SDSS** and all its files from your hard disk.
4. Repeat the steps 1 to 3 to uninstall the **MAP COMPARISON KIT** and **OVERLAY-TOOL**.

2.1.3 WAIKATO SDSS directory structure


When the above described installation of **WAIKATO SDSS** is completed, the files that are part of **WAIKATO SDSS**, **GEONAMICA®** and the **WAIKATO SDSS** case(s) distributed with the installation CD-Rom are ordered in a typical directory structure.



WAIKATO SDSS is typically installed in the directory *C:\Program Files\Geonamica*. Three sub-directories are created: *Waikato SDSS*, *Map Comparison Kit* and *Overlay Tool*. The *Waikato SDSS* directory contains *Geonamica.exe* and all the DLL-files required running the **WAIKATO SDSS** application (see figure below).




The other parts of **WAIKATO SDSS** are the data, simulation files and the intermediate output maps. These are located in *my documents\Geonamica\Waikato SDSS\Simulations*. In here you will find among others several simulation files, recognizable by the extension **.xml*. These files contain the basic information the software needs to run a simulation. Additionally, the simulations folder contains all the data that is used in the simulation. The simulations folder typically contains the following sub-directories and files:



- *Animations*, containing the animation maps relative to the simulations;
- *InputMaps*, containing the base maps relative to the simulations
- *IntermediateMaps*, containing the intermediate output maps for the current simulated year;
- *Legends*, containing the legends of the maps relative to the simulations;
- *Log*, containing the log files relative to the simulations;
- *Land use and Economics.xml*, the simulation file for the prototype version of **WAIKATO SDSS**, specifically including the land use model and the economic model.


2.1.4 MAP COMPARISON KIT directory structure

MAP COMPARISON KIT is typically installed in the directory *C:\Program Files\Geonamica*. The directory *Map Comparison Kit* contains the **MAP COMPARISON KIT** application (*MCK.exe*) and a set of DLL-files (*RasterComparisonModule.dll*, *GeonamicaLib.dll*, *xerces-c_2_6.dll*, *mfc71.dll*, *msvc71.dll*, *msvc71.dll*) required by the application.



Further to this, the other parts of **MAP COMPARISON KIT** are located in *my documents\Geonamica\MCK*. There are four sub-directories in this folder:

- *Examples*, containing examples developed for the **MAP COMPARISON KIT**;
- *Palettes*, containing the map legends for the **MAP COMPARISON KIT**;
- *Results*, containing results generated with the **MAP COMPARISON KIT**;
- *Temp*, containing the temporary outputs (e.g. reference maps) generated with the **MAP COMPARISON KIT**



2.1.5 Starting WAIKATO SDSS


Once it is installed, you can start the **WAIKATO SDSS** application as follows:




- Under the *Windows Start button* and the *All Programs* group, you will find a group called **WAIKATO SDSS**. Click on the **GEONAMICA®** icon.




- **WAIKATO SDSS** will be started and you will see the **GEONAMICA®** application window on your screen.



- A message window appears requiring the license file when you start to use the **WAIKATO SDSS** for the first time. Click the **OK** button on the message window.




- A dialog window opens where you can look for the license file for **WAIKATO SDSS** that you received from RIKS. Select the license file and press the **Open** button of this dialog window.
- The licence files will be created automatically in the same directory as *Geonamica.exe*. After this action, the system will not ask you to open the licence file when you restart to use the **WAIKATO SDSS**.



- Now you can start to use the **WAIKATO SDSS**.

2.1.6 Screen Layout



When you start **WAIKATO SDSS**, you will enter immediately in the application window of the simulation environment. This is the window in which you will run your models. You can arrange windows as you like in the application window. Before a simulation file has been opened, the window is empty except for its *Caption bar*, *Status bar*, *Toolbar* and *Menu bar*. The different components of this window will be described in the next paragraphs.

The Caption bar

The *Caption bar*, also called title bar, of the application window shows the name of the application: **GEONAMICA®**. As soon as a simulation file is opened, the title will be extended with the name of the simulation file.



- To the right of the *Caption bar* three buttons are positioned that enable you to resize the **GEONAMICA®** application window:
- The *Minimize* button to the left allows you to shrink the window to an icon. This is the same as pressing *Minimize* in the *Control* menu box.
- The *Maximize* button in the middle allows you to enlarge the application window to the full size of the screen. This is the same as pressing *Maximize* in the *Control* menu box.
- The *Close* button to the right allows you to close the application window, and thus quit the application. This is the same as pressing *Close* in the *Control* menu box.

The Menu bar

The *Menu bar* of the application window contains **WAIKATO SDSS**'s main menu. The commands are logically organised in the menu so that you will quickly become comfortable with the various functions of the program. The menus are summarised in the table below; subsequent sections elaborate on the description. Section 2.5 gives an overview of all menu commands.

Use this menu	To ...
File	Manage your simulation files.

Simulation	Control the simulation.
Options	Customise the workspace. Commands permit among others to display or remove the Status bar and/or Toolbar, and select types of output
Window	Manage your windows on the screen
Help	not implemented

The Toolbar

The *Toolbar* gives faster access to some of the more frequently used commands that are also accessible via the menu.



Use this Button	To ...
	Open a simulation file from the disk.
	Save a simulation file to disk.
	Advance the simulation with one simulation step.
	Advance the simulation till the next pause is reached.
	Stop the simulation after the current step is finished
	Reset the simulation. Switch the simulation clock back to the initial year of simulation.

Besides this set of buttons, the *Toolbar* also displays the simulation clock. Each time step, the clock is updated to match the current value, which means that it will be incremented by a value of 1 year.



The *Toolbar* command in the *Options* menu gives the option to display or hide the *Toolbar* in the GEONAMICA® application window.


The Status bar

The *Status bar* is displayed at the bottom of the application window. This zone provides information to the user on his actions while he is working with the application. The left area of the *Status bar* describes actions of menu commands as you use the mouse or arrow keys to navigate through menus. Also messages are shown describing the actions of *Toolbar* buttons when pressed. The right area of the *Status bar* indicates which of the following keys are latched down: the Caps Lock key (CAP), the Num Lock key (NUM), or the Scroll Lock key (SCRL).

The *Status bar* command from the *View* menu gives the option to display or hide the *Status bar* in the GEONAMICA® application window.

2.1.7 System information

The different commands in the *Help menu* will permit to look up the system information about **WAIKATO SDSS**, its commands, options, and tools. Use the *Help* menu to select the type of information that you want **WAIKATO SDSS** to display on the screen.



Index

Use the *Index* command to get the opening screen of the on-line help file of **WAIKATO SDSS**. From the opening screen, you can jump to step-by-step instructions for using **WAIKATO SDSS**. Double click the topic that you want help on. Once you open help, you can click the *Contents* button whenever you want to return to the opening screen.


Using Help

Use the *Using Help* command for getting general instructions on how to use the Windows Help System.

Licence


Use the *Licence...* command for getting the licence information on the *Licence* window.

The system allows the user to import the licence file that you received from RIKS by pressing the link of *Read a licence file...* to open the *Open* dialog window.



About


Use the *About...* command to open the *About* window. You will find here the copyright notice and version number of the **GEONAMICA®** application that you are using. The latter is important if you need assistance with the software from the developers (see section 0) or when you request an update of the software.



DRAFT

2.1.8 Closing WAIKATO SDSS

Closing **WAIKATO SDSS** is done by selecting the *Exit* command from the *File* menu. If you have simulation files open and you have made any changes, the application will ask whether you want to save simulation results before exiting.



If you confirm that you want to save changes, you will get the *Set external file names* dialog window. Press the *Yes* button of the *Save* dialog window to carry out the action of saving and exiting. More information on saving simulation results is given in section 2.2.4 of this manual.

2.1.9 If you experience problems

If you experience problems installing or running **WAIKATO SDSS**, please contact us with the version number of the **GEONAMICA®** application that you are using (see section 2.5.5 Help menu):

Research Institute for Knowledge Systems bv.

To the attention of Hedwig van Delden

P.O. Box 463, 6200 AL Maastricht, The Netherlands

Tel: +31 (43) 3501750

Fax: +31 (43) 3501751

E-mail: info@riks.nl

Website: www.riks.nl

2.2 **Running simulations**

This section describes how to run simulations with **WAIKATO SDSS**. It deals primarily with the interaction between the user and the software. Only a global overview of the model itself will be given. For details about the model, we refer to the accompanying reports of **WAIKATO SDSS**.

In the previous section we explained how to install and run **WAIKATO SDSS**. We assume from now on that you have read this information, that you have knowledge of the different technical terms introduced, and that you have successfully installed **WAIKATO SDSS** on your computer.

2.2.1 Opening a simulation


Opening a simulation file

Make sure that you have started the **WAIKATO SDSS** (see section 2.1.5 Starting **WAIKATO SDSS**) and the **GEONAMICA®** application window appears on your screen.



The *Open* dialog window will open. If the *Open* dialog window is not on your screen, press the *Open simulation file* button in the *Toolbar*.

Look in the *Open* dialog window for files with a *.xml* extension which are installed under *my documents\Geonamica\Waikato SDSS\Simulations*.




Navigate through the directories on your hard disk or on another computer in the network, in search of the simulation file of your choice. Once the name of the file appears in the *Open* dialog window, select it and press the *Open* button or double click the file icon.

The *.xml* file contains references to all the files that are required to run a model.

Once all files have been loaded, two windows will appear in the application window: one titled the *Main window* and the *Land use map*. It is not possible to close these windows. You can move them and change their size to organise your workspace, including *Minimizing* or *Maximizing*.

The main window

The *Main window* is divided into two parts: the *Navigation pane* on the left hand side of the *Main window* and the *Content pane* on the right hand side of the *Main window*. The *Navigation pane* consists of 4 *Tabs*: *Drivers*, *Scenarios*, *Indicators* and *Analysis*. If one of the *Tabs* is clicked, the list of *Elements* under this tab appears. When clicking on one of these *Elements*, the underlying contents will be displayed on in the *Content pane* on the right side of the *Main window*. You can expand one of the tabs by clicking on this tab and you can close this tab by clicking another tab.



The *Main window* provides access to the policy user and the modeller. Section 2.3 and section 2.4 provide detailed descriptions of interface for these two types of users.

2.2.2 Editing Input and Displaying output


In **WAIKATO SDSS** system, the inputs and outputs are organised by *map*, *map file*, *graph*, *single value* and *table*. The following sub sections describe how to edit input and display output by the categories of *map*, *map file*, *graph*, *single value* and *table*.

Map window

A *Map window* is split into 5 viewing areas, called panes. Panes are separated from one another by means of *Splitter bars*. The *Land use map* window is a *Map window*. We use the *Land use map* window as one example of *Map window*.

You can freely open and close maps, except for the *Land use map* window. Beware: opened windows are updated while the simulation is running and this consumes processing time, hence the program will be slowed down.

You can displace the splitter bars to change the size of the panes. To this end, position the cursor over the splitter bar. Move the mouse with the left mouse button held down to move the splitter bar and change the size of the panes accordingly.



Splitter bar

Panes are separated from one another by means of *Splitter bars* vertically or horizontally. If contents of the pane are not displayed completely, use the scroll bars to move vertically or horizontally.


Map pane

The pane in the middle of the *Land use map* window – called the *Map pane* – contains a map representation of the modelled region. More in particular, the actual land use map is shown. The *Map pane* is equipped with a vertical scroll bar and a horizontal scroll bar.

In the *Land use map* information is presented per cell. The cells on the map represent the predominant land use on a cell. To the left of the land use map you can find a legend that explains the meaning of the colours on the map. When the simulation is running, the *Land use map* window will be updated and the resulting land-use will be displayed in the *Map pane*.

Legend pane

The legend of the map is displayed in the upper left pane called *Legend pane*. It shows the legend of the selected map in the *Layer Manager* on the right top of the *Map window* (see section *Layer Manager*). For example, if you select land use map, the legend pane shows the legend of land uses.



The land use is classified by 3 states (see section Land use classes): *Vacant*, *Function*, *Feature*. In the Legend of the map, the *Vacant* states appear at the top of the list, the *Function* states are underlined, and the *Feature* states appear at the bottom of the list.

Overview pane

The lower left pane of the *Land use map* window, called the *Overview pane*, shows the whole modelled region. The inverted rectangle shown in this small map localizes the region that is currently displayed in the *Map pane*. If the mouse is placed inside this wire-frame, it can be moved by holding the left mouse button clicked down. While the rectangle is moved, you will notice that the overview of the map in the *Map pane* is changing accordingly. The overview of the map can also be changed by means of the scroll-bars of the *Map pane*.

Layer Manager

The upper right pane of the *Land use map* window called *Layer Manager* shows the layer view of maps: *Land use map* and *District boundaries*. The *Land use map* is a grid layer. You can click the *Layer visibility* button to turn layer visibility on or off.

Use this button	To:
	Turn on the layer visibility
	Turn off the layer visibility

Tool pane

The lower right pane of the *Land use map* window (called *Tool pane*) shows the tools for viewing and editing selected layers. The *Tool pane* includes the *Zoom tools*, *Grid tools*, and *Network tools*. You can open the *Context menu* of the *Tool pane* by right click, which controls how tools are arranged on the desktop. The list below summarized the *Context menu* commands.



Use this button	To:
Expand all	Expand all the tools in map window
Collapse all	Close all the tools in map window
Zoom tools	Change the manner in which different maps of map window are displayed
Grid tools	Edit, check and save grid map
Network tools	Edit and display network map

Zoom tools

When you would like to see a location in more detail you can use the layer manager on the right hand side of this window. In the layer manager you will find the option zoom operations under which you will find the selected buttons:

Use this button	To:
	Zoom in.
	Zoom out.
	Pan on the map to view another location.
	Select a region of the map to zoom in on.
	Fit the entire map in the window.

When you activate one of these buttons and move the mouse pointer to the map, you can carry out the selected option.


Grid tools

You can use *Grid tools* to edit and view the information of the maps that you selected.

Use this Button	To ...
	Change the pointer to a pen. The pen is used to pick a value from the legend and enter it in a cell on the map.
	Change the pointer to a bucket. The bucket is used to pick a value from the legend and enter it in larger, contiguous areas of the map.
	Display the information of the selected map on the map windows
	Copy the shape and color information in the selected area from another grid layer to the current grid layer
	Copy the color information on the selected area from another grid layer to the current grid layer
	Save map that you select

Network tools

You can use the *Network tools* to view and edit the Infrastructure network. In this version of **WAIKATO SDSS**, about how to access the Infrastructure network map, the user can refer section How to view and adapt the road network?



When the Network map is active, the *Network tools* section of the Tool Pane on the right bottom part become active. The network map displays in the *Map pane*. The *Legend pane* consists of 4 legend tabs which are used for editing the legend of Network map.

The Network map is organized by links and nodes in the *Map pane*. Each link in the network map has a range of properties.


- Click the *Select/edit* button, then move the mouse over the interested link, double left click on it or right click on it and select the option *Properties*. The link is selected and displayed in red. The *Properties* window pops up, in which, all the properties of this link are shown in the table of the *Properties* window.
- It enables to change the network as links and nodes can be added or removed interactively. In this version **WAIKATO SDSS**, the *Add link* and *Add nodes* buttons are not available and are therefore greyed-out. In the future version **WAIKATO SDSS**, the user will be able to change the characteristics of links.
- Click on the dropdown list of the *Color master field* to select the property of link *AccType*, whose categories will be used as the *Link color* legend of the network displayed in the *Map pane*: Motorway, Dual carriageway road, Other road and Car ferry. All the properties of link are displayed on the dropdown list the *Color master field*, but only the *AccType* categories are used as color legend. The user can determine or edit the Link color legend by double clicking on the category list. Section Legend editor describes how to use the legend editor.
- Select the check box *Show nodes* to display the nodes of a network in the Map pane.
- Select the check box *Show links* to display the links of a network in the Map pane.

Customizing map output

Each land use map, potential map, neighbourhood effect map and accessibility map in **WAIKATO SDSS** is presented with its dedicated legend. These legends are completely customizable. The legends may contain the colour information for the different classes or they may apply colours from a palette file. That is why this section contains a section about the **LEGEND EDITOR** and a section about the **PALETTE EDITOR**. For typical users it suffices to only use the **LEGEND EDITOR**.

Legend editor

Double clicking on the legend opens the *Legend Editor* dialog window. In the figure below, the window is shown and the relevant settings are briefly explained.



The *Legend editor* dialog window is divided into several areas which contain the information relative to different aspects of the legend:

- On the left, the legend is shown as it will appear in the *Legend pane* of the map window. If one of the classes is double clicked, one can manually adjust the colour of the class and / or its label (for categorical legends) or its range (for numerical legends) in the *Class characteristics* dialog window (see below).
- At the top right are the usual *OK* and *Cancel* buttons.
- At the bottom right is an *Apply* button. When clicked it updates the legend on the left side of the window. Note that the legend of the map will only be updated if *OK* is pressed and will stay unchanged if *Cancel* is pressed.
- In the top centre of the legend editor is the *Palette settings* section, which controls the palette settings. One of the predefined palettes can be selected from the list box. The order of the colours in the palette can be reversed by clicking one of the radio buttons in the section named *Top of legend is*. Finally, one can modify the palette by clicking on the *Edit...* button, which will open the palette editor, as discussed in paragraph 0.
- In the *Legend type* section one can select the legend type and enter the number of classes. If the number of classes is changed the *Apply* button needs to be clicked for the changes to take effect. Only the number of classes and the colour of each class will be changed according to the palette, not the class ranges or labels.
- The items in the *Numerical legend settings* section are only available if the legend type is numerical. If so, the labels of the classes will typically be set automatically by the legend editor. However, you can change the format of the labels in the *Labels* section. You can set both the number of decimals and the label format of all classes. If you set the latter to *Custom*, you can change the labels of each class manually by double clicking on that class in the legend on the left of the window.


A legend is a classification of values in a map and a mapping of those classes to several other characteristics, such as labels, ranges or colours. Basically, there are two distinct types of legends, namely categorical and numerical legends. Categorical legends divide the possible values in a map into categories that have a name and a colour. An example of a map with a categorical legend is the land use map in the *Land use map* window, although you cannot use the legend editor on this map directly. Numerical legends make a partition of a range of values into smaller ranges – the classes – and allocate a colour to each class. Numerical legends are often useful for indicator maps.

When we make such a partition for a numerical legend, the goal is to make a partition that follows the distribution of the values in the map, but also distinguishes extreme values from other values and makes full use of all classes in the partition. Since this is not a trivial task, the legend editor provides some automation in creating a numerical legend.

As a first step, one can specify the total range of the legend in the *Display interval* section or choose for an automatic range that will be set to the range of values in the map. The second step is to select a scaling method to set the class boundaries. The list box in the *Scale* section allows you to select one of the available scaling methods. When a method is selected, the class ranges will be calculated and presented in the legend on the left of the dialog. The legend editor also calculates an estimate of the effectiveness of the chosen scale that can range from 0 to 100%, where more is better. If the *Find best scale* button is clicked, the legend editor will iterate over all available scaling methods and select the one with the highest estimated effectiveness.


A description (see section 2.6 Appendix) is given of the different scaling methods and the way in which the estimated effectiveness is calculated.

Class characteristics dialog



When you click in a colour box in a legend, the *Class characteristics* dialog window opens, enabling you to define the characteristics of a class including the colour to represent the cells that belong to the class. If the legend is categorical, you can also change the label, but not the lower- and upper bounds of the class. If the legend is numerical, you can change the lower- and upper bound of the class and the label, if label format is set to *Custom* in the legend editor.

Palette editor




The **PALETTE EDITOR** allows you to modify a palette manually or semi-automatically. By double clicking on one of the categories on the left side of the window, you can select a colour for that category. Palettes are stored either as palette-files (*.smp) or as a custom palette in the legend. You can create, open and save palette-files with the *New*, *Open...*, *Save* and *Save as...* buttons. To change the number of classes of the palette, change the number in the *Palette size* edit box and then press the Tab key on your keyboard. Clicking on the *Reverse palette* button will swap the colours in the palette.

Clicking the colour box in the palette will open the *Class characteristics* dialog window and enables you to specify the colour of the class. The palette blend section allows for some automation in the selection of colours. You can select a range of classes with the *Lower* and *Upper index* and change the colours of the classes between the two indices to a blend of the colours of the indexed classes. This way, you can easily make a smooth palette that blends from one colour to the next.

Graphs


This graph editor is used extensively in **WAIKATO SDSS** to define two-dimensional relations: time series and distance decay functions. It has two main parts: to the left is a graphical representation of the two-dimensional relation and to the right a list box with the x/y value pairs defining the relation.



The graph can be edited in the graphical part only. Changes made are immediately visible in both parts.

A relation is entered or changed by entering points in the graphical representation. Move the cursor to the abscissa position for which you want to enter a new (ordinate) value. Double click with the left mouse pointer to add a point to the relation. As a result a little circle will be drawn and line segments will connect the new point to the nearest points left and right in the graph created thus far. To reposition a point, click it with the left mouse pointer and move it to its new position with the left mouse button held down. Or, in order to position it to a particular x-y location, click it with the right mouse button and enter the abscissa (x) and ordinate (y) values in the *Edit point* dialog window which opens. To remove a point from the relation, double-click it with the left mouse button.



The ranges of the x- and y-axis can be changed by clicking the *Options* button. The *Options* dialog window will open in which you can enter the lower and the upper bounds of the x- and y-axis.



When the *Grid* check box is checked, a grid is drawn in the graph window.


Single Value and time

Clicking the mouse over the *Text box*, the user can enter or edit a single numerical value directly.



You can use one example of how to use the date and time editor by going to Drivers->Parameters->Land use->Land use parameters. Clicking the mouse over the *Text box* of the

date and time editor, the user can also enter or edit a date and time for map file reloading at the specified date and time (see section Map file).



Tables


The table editor enables the user to enter a series of numerical values. You can use copy and paste functions by pressing the keyboard shortcuts Ctrl+c and Ctrl+v to edit the selected numerical values between the table in **WAIKATO SDSS** and Excel sheets.

Parameters
Inverse Leontief matrix


Sector / Sec...	Horticulture ...	Livestock an...	Dairy cattle ...	Other farming	Services to ...	Forestry an...	Fishing
Horticulture ...	1.01294	0.0124377	0.0192297	0.00756484	0.0103621	0.0109534	0.00:
Livestock an...	0.0354288	1.16261	0.0502031	0.0512455	0.0437754	0.0243183	0.0:
Dairy cattle ...	0.00785599	0.0257647	1.01759	0.0105521	0.0100943	0.00397852	0.00:
Other farming	0.00966101	0.0138343	0.0128085	1.01409	0.0113277	0.00281665	0.0000:
Services to ...	0.117452	0.105247	0.0610444	0.0776804	1.11416	0.127541	0.0:
Forestry an...	0.00754027	0.00878577	0.00953513	0.00865348	0.0033628	1.16203	0.00:
Fishing	0.000238662	0.000367966	0.000760069	0.000887302	0.000277738	0.000203105	1
Mining and ...	0.00570676	0.00910621	0.0116883	0.0103113	0.00209824	0.00319881	0.00:

Map file

The map file editor lets a user add or update maps at the specific date and time.




Before loading a map file, the status of the file is “No file selected”. Click the mouse on the *Browse button* in the table, the *Select dialog* window or the *Open dialog window* for map files will open. Look for files with an .asc, .img, or .rst extension. Once the name of the file appears in the *Select dialog* window or the *Open dialog window* select it and press the Open button or double click the file icon.



Once the file has been loaded, the directory of this map file is shown in the file status cell.

2.2.3 Running a simulation

Once the *Main window* and *Land use map* window have been opened, the program has read the default values for all the parameters as well as the initial values for all the state variables of the model. The program is ready to run a simulation. You can run a simulation with the simulation control buttons in the *Toolbar* or with the commands in the *Simulation* menu.



The most right box displays the *Simulation clock*, which indicates the progress of the simulation: it displays the year until which the simulation has run. The initial year is 2004.

Init

To initialise the simulation, use the *Init* command in the *Simulation* menu. After the model has been initialised, all the variables will display the correct initial condition (values) of the model. If the *Step* or *Run* command is clicked the simulation will be automatically initialised if this has not been done manually.

The *Init* command can also be used to have the model perform a step without advancing the simulation clock. This is especially handy to test the immediate effects of a newly entered (set of) parameter(s) before running the model.

Step

To verify that the program is ready to run, use the *Init* command in the *Simulation* menu or press the *Step* button in the *Toolbar*. Once pressed, **WAIKATO SDSS** will go through a number of essential phases, such as the initialisation and testing of its inputs, which are of no direct interest to the user before it will make one simulation time step. This will take a while. You will notice that the action is finished when the simulation time changes from 2000 to 2001 and the land use map in the *Land use map* window is updated.

If the *Step* command is selected the simulation will be automatically initialised if this has not been done manually.

Run

To perform the simulations for the whole simulation period, use the *Run* command in the *Simulation* menu or press the *Run* button in the *Toolbar*. The simulation will start running till the next pause tab has been reached and the progress can be followed as the *Land use map* window and the simulation progress clock are updated on a yearly basis.

Unless other pause tabs have been set by means of the *Pauses* command (see section Pauses) in the *Simulation* menu, the simulation will halt at the end of the simulation period. If the *Run* command is selected the simulation will be automatically initialised if this has not been done manually.

Once the simulation is running, the user can halt it by selecting the *Stop* command from the *Simulation* menu or by pressing the *Stop* button from the *Toolbar*.

Stop

The simulation can be paused by pressing the *Stop* button in the *Toolbar* or using the *Stop* button in the *Simulation* menu. When the simulation is paused, it will finish the calculations for the current year and then pause. The simulation will continue when the user selects the *Step* or *Run* command from the *Simulation* menu or when the *Step* or *Run* button from the *Toolbar* is pressed.

You can also pause the simulation at predefined instances, by using the *Pauses* command (see section Pauses) in the *Simulation* menu.

Reset

You can switch the simulation clock back to the initial year of the simulation or undo the simulation step by pressing the *Reset* button in the *Toolbar* or using the *Reset* button in the *Simulation* menu. The input information of the model is not affected by resetting the simulation. Hence, corrections made to parameters and maps, such as suitability maps, zoning maps, network maps, are not affected. However, after resetting the simulation, the state variables, including the dynamic maps are calculated again for the initial year and on the basis of the available input information.

Since we have not changed parameter values remaining unchanged is of no importance now, but it will be an important issue once you will be changing parameter settings while running and testing different scenarios and planning options with the system.

Pauses


To set the pauses of the simulation, use the *Pauses...* command in the *Simulation* menu. When *Pauses...* is selected, the *Pause Settings* dialog window opens. Use the *Run* command in the *Simulation* menu or press the *Run* button in the *Toolbar* to advance the simulation till the next pause is reached.



Display format


In the *Display format* pane of the *Pause settings* window, you can define the display format of pause instants by clicking the radio button in front of the format that you want to display. When you switch the format, the list of pauses is displayed according to the format that you selected.

Be aware that the *Display format* that you defined in the *Pause settings* dialog window will be used for the overall time in the system, such as the time format in the *Log maps* in the *Options* menu and *Simulation clock* on the *Toolbar*.





Add

You can add a new pause by pressing *Add* on the right hand side of the *Pause Settings* dialog window. Enter the year in which you want to halt the simulation in the *Time* text box and then press *OK*. The pause at this year will be added to the *Pauses* list.



Generate

You can predefine instances by using the *Generate* command. The *generate pauses* dialog window opens when you press the *Generate* button of the *Pause settings* window. You can enter the interval start time, the interval end time and the interval step length of the *generate pauses* window and press *OK* button. The pauses are generated and displayed on the *Pauses list* of the *Pause Settings* dialog window.



Remove

You can remove a pause by selecting the pause year that you want to remove and pressing *Remove* button on the right hand side of the *Pause settings* window.

2.2.4 Saving simulation results

Working with a simulation model is to a large extent an iterative process. The user explores different combinations of interventions and alternatives to interactively learn which are likely to satisfy the preset criteria. These explorative exercises require a capability of storing simulation results in an efficient manner.

The *.xml* file contains parameters and references to all the maps that are required to run a model and the output maps of the model for the simulated year. Saving simulation results includes saving the parameters and maps of the simulation. They are saved in different ways.

Saving parameters

- Before you save the simulation, the changes of parameters that you made in your model are only processed after you press *Reset*, *Init*, *Step* or *Run*.
- If you try to save a simulation without doing this, a message will appear reminding you.

Saving maps


- You can save the output maps for the current simulated year by going to the *Save simulation* or *Save simulation as* option in the *File* menu.
- You can specify the directory of maps that you want to save in the opened *Set external file names* dialog window.

Beware that you should press *Reset* button if you want to save (or save as) the simulation in the start year; otherwise, the simulation for the current simulated year will be saved.

Save simulation

The *Save simulation* command from the *File* menu allows you to store simulation results to the current simulation file in sophisticated ways. More in particular, it enables you to efficiently manage the individual files that constitute a single simulation. A single simulation run can generate anywhere from 1 to dozens of files per simulation step. Hence, if all these files would be saved, storing a large number of simulation runs would require much storage space on your hard disk.

When you select *Save simulation* from the *File* menu, the *Set external file names* dialog window opens. The *Set external file names* dialog window displays an overview of all the data files that are used in the current simulation: their respective names and paths.




If you are a relatively new user of **WAIKATO SDSS**, press the *Save* button to complete saving the simulation and skip the remainder of this section. If however you are more experienced with the system, this dialog window will help you to change the composition of your simulation file before saving it.

- Keeping the same directories for all data files: If you press the *Save* button in the *Set external file names* dialog window, all the data files on the list will be saved in the default directories which are configured in the current simulation file.
- Changing the directory or the file name of each data file: The system allows you to specify the directory where you want to save each data file by left clicking on the path name in the *File Name* text box. Once it is selected and marked blue, you can type any path or file name you want. The system allows you to change the format of data file by clicking  and selecting the appropriate data type from the drop down list.
- No file: The data file marked as “-” on the *File name* list indicates this file is not used or not required for the current simulation. You can always use the *Reset* to undo the changes in the table.

Once you press the *Save* button of the *Set external file names* dialog window, the current simulation file will be overwritten, and the original information will be lost. Overwriting files can be avoided simply by choosing another file name than the current one (see section *Save simulation as*).

Save simulation as

The *Save simulation as ...* command from the *File* menu allows you to store simulations with to another file name. When you select *Save simulation as ...*, the *Save simulation file* dialog window opens, requesting you to enter the name of the file.




If the name of the current simulation file is entered, the system asks you whether you want to replace the existing file. If you press *Yes* button of the *Save* dialog window, the *Set external file names* dialog window opens. You can find the description of the *Set external file names* dialog window in section *Save simulation*.

The *Save simulation as...* command and the *Save simulation* command will only save the model for the current year in the simulation – that is, current values of state variables and parameters. It will not store intermediate results. To save these, you should make use of the *Write to Excel...* command, the *Log maps...* command and the *Animate maps...* commands from the *Options* menu. You will find more information on these in section *Write to Excel*, section *Log maps* and section *Animate maps*, respectively.

Write to Excel


Select the *Write to Excel...* from *Options* to establish (or interrupt) a link between **WAIKATO SDSS** and a Microsoft Excel Workbook. A new window appears as shown below. This link is a DDE (Dynamic Data Exchange) link. Via this link **WAIKATO SDSS** is sending model output to the Workbook while the simulation is advancing.



The data transferred to the Excel workbook shows results for the national and the regional level, as well as summarized information for the land use model.

Defining Excel sheet name


The list of predefined output options are displayed per model block from which they origin in the *Model block name* column on the upper pane of the *Write to Excel settings* window. The system will only make links for the model blocks which have been configured in the column of *Excel sheet name*. You can enter a name on the list by left clicking the cell next to this block. The names that you add in the *Write to Excel settings* window will be displayed as the names of the sheets in Excel.





Defining writing moments

While a simulation is advancing, the system only writes model output for the moments that are determined in the *Writing moments* pane on the low left part of the *Write to Excel settings* window. You can adjust the list of writing moments by using the *Add...* button, the *Generate...* button, the *Delete* button and the *Reset* button.

- You can add a single moment by pressing the *Add...* command. The *Add write moment* dialog window opens and you can enter the moment for which you want to display the model outputs in the Excel workbook. Then press *OK*. The write moment at this year will be displayed on the *Writing moments* list immediately.




- You can define log moments at regular intervals by pressing *Generate...* command. The *Generate log moments* dialog window now opens where you can enter the interval start time, the interval end time and the interval step length. Press *OK* button afterwards. The pauses are generated and displayed on the *Writing moments* list immediately.




- You can easily delete one or several writing moments by selecting the moments that you want to remove and pressing *Delete*.
- If you are not satisfied the moments that you just set up, you can undo the configuration of the writing moments by pressing the *Reset* button. This action will reset all writing moments to the value they had when you last opened the *Write to Excel settings* window.

Starting writing

To finalise the link between **WAIKATO SDSS** and Excel workbook, press the *Start writing* button on the right low pane of the *Write to Excel settings* window. The *Write to Excel settings* window closes automatically. A link between **WAIKATO SDSS** and Excel workbook is established after this action, although you cannot see this directly on your screen.




While this function is activated, *Write to Excel* on the *Options* menu is preceded with a tick mark. Now you can run the simulation with the link to the Excel workbook.



Saving settings

The system allows the user to change settings for write to Excel while the simulation is running. To do so, click the marked *Write to Excel* option in the *Options* menu. The *Write to Excel settings* window opens again. Now the *Save settings*, and the *Open Excel workbook* buttons are available on the right low pane of the window.

You can only change the settings of in the *Writing moments* but you cannot change settings in the *Excel sheet name* pane that are greyed-out.




It is very important to press the *Save settings* button to finish the adjustments while keeping the system writing model output to the Excel workbook. Only the moments, which are later than the current simulation time, will be written to the Excel workbook. The function of *Write to Excel* in the *Options* menu is still preceded with a tick mark.

If you press the *Open Excel workbook* button, the function of *Write to Excel* will be switched off. You can always check whether the link to Excel is activated from the tick mark *Write to Excel* in the *Options* menu.

Opening Excel workbook


To stop writing to Excel and view the Excel workbook, press the *Open Excel workbook* button. The workbook opens immediately, showing the worksheets with the names that you defined. You can use it now for further analysis of the simulation data.



Note that in order to establish a successful link, it is required that Excel is installed on your machine. If **WAIKATO SDSS** cannot find Excel, the menu option will be greyed out.

Log maps

Use the *Log maps...* command in the *Options* menu to store all the maps produced by the system in the form of .rst files. You can analyse these logged maps files with the **MAP COMPARISON KIT** – see section 2.2.5 Analysing results. When this command is selected the *Log settings* dialog window opens.




Selecting maps

In the *Selected maps* pane, a tree of maps is available, which is organized by the type of information on the map. You can expand or collapse the branches of map tree by moving the mouse over the name of group and left click. In this tree, you can indicate which maps you want to store. To this effect, click on the check box just left of the name of the map of your choice. Maps are selected for logging if the check box is checked with a green mark.

Changing path of log maps

The program automatically sets the path for files where the maps are stored, as shown in the *Log folder* pane. But it is import to specify and group the path for log files relative to the simulation that you are running. Otherwise, previously logged maps will be overwritten.

To modify this path, click the *Browse* button on the right side of the text box and the *Browse for folder* window opens. You can select a folder by moving the mouse over the folder where you want to store the log files and click. you can also specify the location in a sub folder under the selected folder by pressing the *Make new folder* button. Press the *OK* button to finish the action of changing the path for a log maps.




Editing log moments

In the *Log moments* pane on the low left part of the *Log settings* window, you can specify moments for which maps will be logged. You can make a list of logging moments by using the *Add...* button, the *Generate...* button, the *Delete* button and the *Reset* button of the *Log moments* pane. This works similarly to Defining writing moments in the *write to Excel*.

The system allows you to change the display format on the *Add write moment* and *Generate log moments* dialog windows by using the *Pauses...* command in the *Simulation* menu (see section Pauses). You can change the settings in the *Selected maps* pane and the settings of in the *Log moments* pane while the simulation is still advancing.

Turning logging on

To active the logging functions, you have to press the *Turn logging on* button on the right low pane of the *Log settings* dialog window. The selected maps in the tree of maps will be stored in the path you specified. The function of *Log maps* in the *Options* menu is proceeded with a mark.




Saving settings

Press the *Save settings* button to finish any adjustments made in the *log settings*. Only the maps for the moments, which are later than the current simulation time when pressing *save settings*, will be logged. The function of *Log maps* in the *Options* menu is still with a tick mark when it is activated.


Turning logging off

To stop the logging functions, press the *Turn logging off* button on the right low pane of the *Log settings* dialog window. The function of *Log maps* in the *Options* menu is displayed without a mark.



Animate maps

It is also possible to make movies of dynamic maps during a simulation and store them for later use. To that effect use the *Animate maps...* command from the *Options* menu. When this command is selected the *Animation settings* dialog window opens. Animations are stored in the form of *.gif* animations.




Selecting maps

In the *Maps to animate* pane, the tree of maps is shown, which is organized by different groups. You can expand or collapse the branches of map tree by moving the mouse over the name of group and left click. In this tree, you can indicate which maps you want to animate. To this effect, click on the check box just left of the name of the map of your choice. The map is selected for animating if the check box is checked with a green mark.

Changing path of animation maps

The program automatically sets the path and name of the file where the animations are stored in the *Animation directory* text field. You can change the filename and location where the information will be stored by pressing the *Browse* button on the right hand side.

When the animation function is activated in the **WAIKATO SDSS**, this is indicated with a mark in front of this option in the *Options* menu. If no map is selected in the *Animation settings* dialog window, no animations will be generated during the simulation.



You can view the animations in most, if not all, recent Internet browsers as well as some graphics packages equipped with an animation facility.

2.2.5 Analysing results

The system can create a link between the **WAIKATO SDSS** and the **MAP COMPARISON KIT** to analyse results. To activate the **MAP COMPARISON KIT** from the *Main window*, click the *Analysis* tab from the *Main window* and press *Map Comparison Kit*.



The Map Comparison Kit comes with its own dedicated manual which is delivered as an integral part of the **WAIKATO SDSS** package. It explains the use of the **MAP COMPARISON KIT (MCK)**. It describes in detail how you can analyse and compare the .log files generated by **WAIKATO SDSS** in an interactive manner. All .log files generated by **WAIKATO SDSS** are compatible and can be read into the **MAP COMPARISON KIT** in a straightforward manner.


One example about how to use *Map Comparison Kit* to compare scenarios for Policy user is given in section 2.3.6 *Analysing results*.

2.3 Policy interface

The user interface of the **WAIKATO SDSS** system provides access for two types of users: the *policy user* who carries out impact assessment studies related to the impact of certain policies under a range of external conditions and the *modeller* or the *scientific user*, who is responsible for the underlying (scientific) information of the system and needs to adapt underlying data and parameters when more knowledge becomes available over time.

The *Main window* provides access for both types of users. The structure of the *Main window* is available in section Map window. Here we will first explain how the policy user can use the system and then how the modeller can access the models.


The *policy user* finds access to all information relevant for analysing the impact of policies and external factors on the left hand side of the *Main window*. Information is organised in such a way that the user can carry out a structured analysis. It follows the steps *Drivers*, *Scenarios*, *Indicators* and *Analysis*, each of which is explained in more detail below.



2.3.1 Overview of the policy interface

This section gives a brief overview of the different steps a user can take to carry out a policy impact assessment with **WAIKATO SDSS**. In the following sections each step will be explained in detail.

When clicking on the *Drivers* button on the left hand side of the system you get access to the driver section and the different types of drivers become visible: *External factors*, *Policy measures* and *Parameters*. The first two are part of the policy analysis functionality of the system; the latter is the way scientists or modellers can get more detailed access to the underlying models, their data and their parameters. Clicking on each of the driver type icons opens the settings for this driver or set of drivers on the right.



Step 1: Setting up the drivers

In the first part of the analysis, *Drivers* can be introduced and/or adapted. *Drivers* are incorporated in the system are organised in two groups: *External factors* and *Policy measures*. When you click on one of these, you get access to the underlying information. This is also the entry point for adapting drivers and entering new data.

The result of this step is a set of sub-scenarios for each of the drivers. When developing a sub-scenario the user can build on existing sub-scenarios. For example, for the driver *External factors*, a baseline sub-scenario is incorporated in the system that includes all the baseline information from the Economic model. If a user wants to build on this scenario he or she simply loads the baseline scenario, makes the required changes and saves it under a different name.

Since the different drivers are organised per discipline it is also possible that different users (with different expertise) prepare sub-scenarios for different drivers. The sub-scenarios is not yet included in the current version of **WAIKATO SDSS**.

Drivers that are including in **WAIKATO SDSS** are the following:

- External factors
 - Economic drivers: international exports, interregional exports, gross fixed capital formation and changes in inventories.
 - Population drivers: fertility rate, migration rate and mortality rate
- Policy measures
 - Economic options: rates of change in eco-efficiency and rates of change in labour force productivity
 - Zoning measures
 - Infrastructure

Steps required to view or change driver settings are described in section 2.3.2 Setting up the drivers.

Step 2: Creating integrated scenarios

In the second step, integrated master scenarios can be assembled from a selection of the sub-scenarios constructed in step 1. For each of the drivers you need to select the desired sub-scenario. Drivers that are incorporated in the current version of **WAIKATO SDSS** are:

- Policy measures (Zoning, Infrastructure)
- Population
- Economy

When clicking on the *Scenarios* button in the main window you gain access to that part of the interface where you can construct your integrated scenarios or upload a pre-defined scenario.

Steps required to create integrated scenarios are described in section 2.3.3 Creating integrated scenarios.

The part is not yet included in the current version of **WAIKATO SDSS**.

Step 3: Running the simulation

Before running any simulation you can decide which results you would like to save to disk while the simulation is running. **WAIKATO SDSS** has three ways of saving results:

- Link to Excel (for all results at the local level, district level, region level and the NZ&World level): When this option is enabled all selected model output will be directly written to Excel and can be used for analyses and post-processing after the simulation is finished.
- Log (for all map results): When this option is enabled all selected model output will be saved as .rst maps that can be opened in the **MAP COMPARISON KIT** (part of the **WAIKATO SDSS** package) or common GIS packages, for further analysis after the simulation has run.
- Animations (for all map results): When this option is enabled all selected model output will be saved as little movies in Animated GIF format that can be opened in a viewer, but can also be readily incorporated in presentations.

For details about running a scenarios and saving simulation results, please go to section 2.3.4: Running a simulation.

Step 4: Visualising indicators

After running a simulation, the **WAIKATO SDSS** offers several options to analyse results. The first option is to visualise the indicators that are being calculated by the system. The indicators are organised in three groups:

- Economic indicators
- Environmental indicators
- Social indicators

On a yearly basis each of these indicators is calculated. Depending on the type of indicator, it is calculated at one of the spatial levels (NZ & World, Region, District or Local) or at several spatial levels. When clicking on the *Indicators* button in the main window you gain access to the indicators. Steps to take in visualising indicators are described in section 2.3.5: Visualising indicators.

Step 5: Analysing results

The final step of the impact assessment study is to analyse results within a scenario (e.g. the temporal evolution of a scenario) or to compare a set of scenarios. In step 3 of the assessment you have selected what type of information you would like save for analysis, in this step you carry out the analysis. The Excel files that have been created can be analysed with Excel; the animations can be shown in a viewer; and the maps that have been saved in log-files that can be opened in the **MAP COMPARISON KIT**, which can be opened when going to the *Analysis* part of the *Main Window*.

2.3.2 Setting up the drivers

In this section you will become familiar with the different drivers in the system and learn how to enter and change information related to these drivers. There are 3 sections under the *Drivers* tab: *External factors*, *Policy measures* and *Parameters*. Among them, the *Parameters* section is relevant only to a *modeller*. The detailed description about the *Parameters* section will be found in the next section 2.4 Modeller interface.

When you start the system with the simulation file *Land use and Economics.xml* all baseline data is loaded into the system. In the following sections you will learn how to view and change the baseline information step by step for each of the drivers in the system. Creating new sub-scenarios for the individual drivers can be done in two ways:

- By building on the baseline information. In this case adaptations are being made to the data that comes up when you open *Land use and Economics.xml*.
- By building on information in other sub-scenarios. In this case you first have to load a sub-scenario for a specific driver and subsequently you can make your adaptations to this sub-scenario.

Both options will be shown in the following sections.


External factors



When you click on the *External factors* button on the left hand side of the *Main window* you will see that the right hand side of this window changes in such a way that you get access to the *External factors* that are included in the current version of **WAIKATO SDSS**:

- Economy
- Population
- Climate¹

¹ In **WAIKATO SDSS**, Projected changes to 2050 of New Zealand annual rainfall, temperature and potential evapotranspiration (PET) corresponding to three Intergovernmental Panel on Climate Change (IPCC) global greenhouses gases emissions scenarios (low, mid-range, and high) have been produced. The projections are based on the average of output from 12 Global Climate Models (GCMs) compiled for the IPCCs Fourth Assessment Report (AR4). GCM output is statistically downscaled to a 0.05° lat/long (approximately 5km) spatial resolution for all of New Zealand. Since the user can only select one of those scenarios, but not change the contents of the individual scenarios, the scenarios are not available in the *Drivers* part of the *Main window*. They can however be selected in the Scenarios part of the main window.



In the top part of the *Economy* part, you see a drop down list from which you can select the sector that you are interested in.


When you have the *External factors* in front of you, you can carry out the following actions:

- View historic data
- View scenario data (future assumptions)
- Adapt historic and scenario data
- Load an existing scenario (not yet included in the current version)
- Make changes to an existing scenario and save its results (not yet included in the current version)

Since the steps are very similar for all external factors we take *Economy* as an example to explain how you can work with the external factors.

Viewing historic data and scenario data

- Go to the *Driver* section of the *Main window*.
- Click on the *External factors* icon.
- Go to the *Economy* part.
- Select from the drop down list the sector that you are interested in.



There are four economic variables for each sector: *International exports*, *Interregional exports*, *Gross fixed capital formation* and *Changes in inventories*. You can view and edit the values of these variables for each sector. You can click on the *graph icon*  behind *International exports* to have a graph pop up. This graph shows *International exports* in mln NZ\$ (2004) on the y-axis and the year is on the x-axis. You can press *Cancel* to go back to the *Main window*.

Adapting values for external factors

- Go to the *Driver* section of the *Main window*.
- Click on the *External factors* icon and choose from the drop down list in the economy pane the sector *Horticulture and fruit growing*.
- Click on the *graph icon* behind *International exports* to open the graph that shows you the *international exports* from 2004 to 2031.


There are several ways to enter new data points in the graph. The first way is to drag the bubbles in the graph to their desired value. You can also enter the precise values by clicking on a bubble with your right mouse button or by clicking on a value in the list on the right hand side of the graph. More bullets can be added by double clicking with the mouse in the graph and bubble can be deleted by double clicking again on a bubble.

- Remove all points (bubbles) for which you do not want to provide scenario information.
- Note: Changing the first bubble (2000) does not have an impact on your simulation. This data is fixed to ensure consistency throughout all layers. Moreover, it is not possible to remove the final bubble.
- Add any bubbles for years you would like to provide scenario information for.
- Drag the bubble(s) of the year(s) you would like to change to the desired location or click with the right mouse button on the bubble to enter the exact values for the year and the *international exports*.
- Press the *OK* button to save your results and close the graph.

You have now adapted the *international exports* for the *horticulture and fruit growing* sector. After you have created a new sub-scenario for a driver you can save this sub-scenario By pressing the *Save* button on the bottom of the *Main window*.

The system now allows you to choose between updating the present scenario or creating a new scenario. Note that you are not able to update sub-scenarios that are part of the 5 predefined scenarios incorporated in **WAIKATO SDSS**. In case you are working with one of those sub-scenarios the system will automatically inform you that you can only save the sub-scenario under a new name.

To save the sub-scenario you have just created under a new name select *New* and Press *OK*.



A dialog window opens in which you can enter the name of the scenario and the short description.

- Give your scenario a new name in the text box of *Scenario name* and give a description of the scenario in the text box of *Notes* (something that makes it easy for you to remember the scenario by).
- Press the *OK* button.

You have now created a new sub-scenario for *international exports* for the *horticulture and fruit growing* sector. This sub-scenario can be used in the next step of the policy impact assessment: Creating integrated scenarios.

How to load an existing population scenario?

- Go to the *Driver* section of the *Main window* and click on the *External factors* icon.
- Press the *Load Scenario* button on the bottom left side of the window and subsequently selecting your scenario of choice in the dialog window that pops up.
- Press *OK* to finalise the steps for loading a new sub-scenario.

How to make changes to an existing population scenario and save its results?

- Load an existing scenario as explained in the section: ‘How to load an existing population scenario?’.
- Make your desired changes as explained in the section Adapt values of external factors.
- Press the *Save* button on the bottom of the *Main window*.

The system now allows you to choose between updating the present scenario (the one you have selected to load) or creating a new scenario. To create a new scenario select *New* and Press *OK*.

A dialog window opens in which you can enter the name of the scenario and the short description.

- Give your scenario a new *name* and give a *description* of the scenario (something you can remember the scenario by).
- Press *OK*.

You have now created a new sub-scenario for an external driver.

The load scenario and sub-scenario is not yet included in the current version.

Policy measures

In the current version of **WAIKATO SDSS**, the *Policy measures* section is organised by *Economy*, *Zoning* and *Infrastructure* parts.



On the right hand side of the *Main window* you will find an overview of *Policy measures*:

The screenshot shows the 'Policy measures' window with three main sections:

- Economy:** A dropdown menu for 'Sector' is set to 'Horticulture and fruit growing'. Below it, 'Rates of change' are listed: 'in eco-efficiency: 0.500000 % / year' and 'in labour force productivity: 0.440000 % / year'.
- Zoning:** 'Land use type' is a dropdown menu. 'Enactment date phase 1' and 'Enactment date phase 2' are both set to '11/27/2008'. There is an 'Edit map' button.
- Infrastructure:** A section for 'Network changes' with an empty text area and three buttons: 'Add', 'Delete', and 'View current network'.

You can find the *Economy* part on the top right of the *Policy measures* window. Here you can adapt the values of *Rate of change in eco-efficiency* and *Rate of change in labour force productivity* for each sector.

How to adapt values of economy measures?

- Go to the *Driver* section of the *Main window* and click on the *Policy measures* icon.
- Go to the *Economy* part on the top of the *Policy measure* window and select your sector of interest in the drop down list on the top the window.
- The value shown is the one for the sector you have selected. The units are also provided for your information.
- Now click on the text box behind the *Rates of change in eco-efficiency*, click on the value and subsequently type in a new value.

You have now changed the value of the Rates of change coefficient for a certain sector.

The screenshot shows the 'Zoning' section of the 'Policy measures' window:

- 'Land use type' is set to 'Residential - Lifestyle'. There are 'Edit map' and 'Import map' buttons.
- 'Enactment date phase 1' is set to '1/ 1/2015'.
- 'Enactment date phase 2' is set to '1/ 1/2030'.

Besides economic policy measures, the **WAIKATO SDSS** also incorporates measures for zoning regulations and infrastructure. These measures can be found by clicking on the *Policy Measures* button under the *Drivers* tab on the left hand side of the *Main window*. In the middle part of the window you can enter and display the zoning information, the bottom part is reserved for infrastructure. First, you will learn how to change a *Zoning Map*. Next, the options related to the *Infrastructure network* will be explained.

Zoning maps represent the policy part of the land use allocation process. Different locations have different restrictions for different land use functions. Areas where one land use is allowed, like forest reserves for the land use forest, can be restrictive for other land use functions like residential or manufacturing. For this reason there is a specific zoning map for each main land use functions incorporated in the system: *residential, commercial, community service, aquaculture, horticulture, biofuel cropping, vegetable cropping, other cropping, dairy farming, sheep,beef or deer farming, other agriculture, forestry and manufacturing*. The vacant land uses such as *bare surfaces* do not have a specific zoning map since we assume that this land use is allowed everywhere, but that there are no areas where it is specifically planned. In general,

vacant land uses are the land uses that appear when (agricultural) land is abandoned and also the land use that can easily be taken over when population or economic functions expand.

The zoning maps that you find in **WAIKATO SDSS** are pre-processed externally to the system by a combination and interpretation of different zoning plans. The **WAIKATO SDSS** system comes with a tool, the **OVERLAY TOOL**, which is specifically designed to create zoning maps based on a number of spatial zoning regulations. For more information about the **OVERLAY TOOL** please contact RIKS (info@riks.nl).

When more information on zoning plans becomes available, this can be incorporated in the zoning maps, either by the project team, or by the users themselves. In the following steps you will learn how to display and change the zoning maps.

How to view and edit a zoning map or import a new zoning map?

- Make sure that you have the *Policy measures* window in front of you.
- Go to the *Zoning* part in the middle of the content pane of *Policy measures* window.
- Select the land use function of interest from the dropdown list on the top of the *Zoning* part.
- Open the *Zoning Map* for this land use by clicking the *Edit map* button.

In the zoning map you will find four different classes: Allowed, Allowed from time 1, allowed from time 2 and Prohibited. As you can see from these classes, restrictions can be relieved over time.

To edit the zoning map you have just opened:

- Open the *Zoning Map* for the land use of interest by selecting this land use and clicking the *Edit map* button.
- Enlarge the *Zoning Map* until you can see the individual cells.
- Select the *Pen* or the *Flood* option to draw the desired zoning plans. You can select the category you want to draw by clicking on the radio buttons in front of the legend items.
- Close the *Zoning Map*.

To import a new zoning map:

- Select in the drop down list the land use for which you would like to import a new zoning map.
- Press the *Import map* button. A window named *Import zoning map* will open.
- Select in this window the file you would like to import and press *Open*. Note: Make sure the map you import has the same size, resolution, projection, x and y coordinates and categories as the original zoning map and that it has file extension *.rst*.
- Now press *Edit map* to verify that you have uploaded a new zoning map.
- Close the *Zoning Map*.

How to view and adapt the road network?

The relationship between land use and transport systems is generally recognized, by planning professionals as well as scientists. Also, and importantly, it is recognized that the relationship is reciprocal, which means that developments in land use are in part a consequence of the transport system and, at the same time, developments in the transport system are by large the effect of land use changes.


The current version of **WAIKATO SDSS** only incorporates a one-way interaction from transport on land use. In future versions a transport model can be incorporated with which the impact of land use on transport can also be calculated.

In the **WAIKATO SDSS** infrastructure is represented as a network layer. Accessibility coefficients, which describe the importance for certain land uses to be close to elements of the infrastructure network, play an important role in the allocation of the land use functions. Policy decisions related to the changing accessibility are mainly the construction of roads, railways and (possibly) irrigation networks. In this exercise you will learn how to adapt the road network.


There are two ways to introduce a new road; you can either do it by drawing a line in the user interface of **WAIKATO SDSS**, or by introducing it as a shape file. Since the manually drawn segments are often inaccurate and not connected to the rest of the road network, it is advisable to introduce the new road in a GIS first. For the sake of the exercise however, we let you draw the road in **WAIKATO SDSS**.

- Go to the *Policy measures* section of the *Main window*.


Looking at the bottom part of this window you will see the information related to infrastructure. We now assume that we want to change the network in 2012.



- Press the *Add* button on the right hand side of the *Infrastructure network* dialog window and –since we want to introduce a change in 2012– change the date to *2012-Jan-01 00:00:00* in the dialog window that comes up. Press *OK*.
- Select the newly created layer by clicking on the date *2012-Jan-01 00:00:00*.



- Press the button *View current network and selected changes*. First, you will be asked to name your new layer. Give it a name of choice and press *Save*. The network pops up in a new window.



- Go to *Zoom tools* on the right hand side of the Map window and select one of the zoom options.
- Go to the map and *Zoom in* on your region of choice.


The transport network is not yet included in the current version of **WAIKATO SDSS**.

Summary

In this section you have become familiar with the different drivers in the system. In the next section you will learn how to combine these sub-scenarios to create integrated master scenarios.

2.3.3 Creating integrated scenarios

In the previous sections you have read how to adapt the different drivers that are incorporated in the system. Furthermore, you have learned that each of these drivers can be stored in different sub-scenarios.



To create a new scenario you go to the *Scenarios* tab of the *Main window* and click on *Scenario manager*. Here you select for each of the drivers that you see on the right hand side a sub-scenario from the drop down list. Note that new sub-scenarios that you might have created for different drivers are also available through the drop down list.

- Press the *New...* button to create a new master scenario
- Name the master scenario and give it a description and press *OK*. Your new scenario is created!
- If you want to carry out a simulation with your new scenario, press the *Load scenario data* button on the bottom of the window to load all data of the selected scenario into the system.

Besides creating scenarios, **WAIKATO SDSS** offers the possibility to delete master or sub-scenarios. You can delete master scenarios by selecting them and pressing the *Delete* button next to the *New...* button. You can delete sub-scenarios by selecting them and pressing the *red cross* behind them. Be careful: you can only delete sub-scenarios that are not part of an existing master scenario!

The scenario manager is not yet included in the current version.

2.3.4 Running a simulation

A more general description about running simulations is available in section 2.2. In this section you will learn how to run a simulation and save its output results while running this simulation.

Saving output results

Obviously you cannot investigate all land use changes, as well as other available information, while the model is running. Therefore you have several possibilities to export intermediate and final results of a simulation:

- You can take an individual map and export it to analyse it;
- You can create a log file, that contains a series of maps to be analysed afterwards;
- You can make an animation that shows you the land use, indicators or other model results change over time as a movie;
- You can create a link to Excel through which all selected model results are directly written to Excel.

Exporting individual maps

To export a map you need to have the map open in your active *Map window*. In this window you will find the *Save grid* button in the *Tools* pane on the right low part of the window (see for example the *Land use map* window).

Clicking on this button allows you to export the map to the folder you like. There are several different file types that you can choose to export maps, from these the Arc ASCII format (*.asc) and the IDRISI raster format (*.rst) the most common formats. These file types can be used in the **MAP COMPARISON KIT (MCK)**.

Creating log files

Log files are actually files that contain a reference to one or several maps. You can decide yourself how many maps you want to store for eventual analysis. Log files can also be opened in the **MCK** for further analysis. Log maps can be created by clicking on the option *Log maps...* in the *Options* menu as described in 2.2.4. When turning on the log functionality, remember that maps with a resolution of 200m will use some disk space.

Creating animations

Animations are movies that show the spatial developments (e.g. land use, total potential, ...) over time. They come as a *.gif file which you can play in a web browser or picture viewer. Animations can be created by clicking on the option *Animate maps...* in the *Options* menu as described in 2.2.4.

Writing model results to Excel

Model results can be written to Excel by clicking on the option *Write to Excel* in the *Options* menu. A *Write to Excel settings* window pops up that allows you to select what information you would like the **WAIKATO SDSS** system to write to Excel. For a detailed explanation on how to write information to Excel, go to section *Write to Excel*.

Running the simulation

Land use change has a spatial as well as a temporal aspect. The spatial aspect is visible in the form of a map; the temporal aspect is incorporated in the computation of yearly time steps, rather than giving one final situation. Hence the **WAIKATO SDSS** is a dynamic system.

To run a simulation, you have the following basic options, which are also described in the table in section *The Toolbar*. You can find these buttons in the *Toolbar* on the top of your screen, but you can also access to them through the *Simulation* menu):

- When you press *Step*, **WAIKATO SDSS** computes the change for one year.
- *Run* lets a simulation run until the final year. By default 2031 is the final year for this version of **WAIKATO SDSS**. The final year of simulation of the next version will be 2050.
- *Stop* lets the simulation stop at the end of the year it is currently computing.
- *Reset* finally resets the simulation to the initial starting year, in this case 2004.

Besides the basic functionality there are three advanced options to run a simulation: *Init*, *Pauses* and *End year....*. These options can be found through the *Simulation* menu.


2.3.5 Visualising indicators

The basic output **WAIKATO SDSS** produces is information about land use, climate, hydrology, water quality, economy, environment and population. However, these numbers and figures are not always easy to interpret at first instance. For that reason, **WAIKATO SDSS** offers the opportunity to compute indicators as well. An indicator in this context is a measure to make a particular phenomenon perceptible that is not –at least not immediately– detectable.

Indicators are organised in three groups in the user interface:

- Social indicators
- Economic indicators
- Environmental indicators

Some of these indicators describe a state (e.g. the *land use map*) or a condition, others a change over time(all indicators with units *.../year* are indicators showing a change over time. e.g. the *Annual runoff*). The first set of indicators is already available when starting up the simulation; for the second set the simulation needs to take a step first, otherwise the change between two years (current year in the simulation and start year of the simulation) cannot be calculated.




You can visualise indicators at any point in time (any year) during the simulation. To visualise an indicator, take the following steps:

- Go to the *Indicators* tab of the *Main window*.
- Select the sections on the left hand side on the *Main window* the type of indicator you are interested in: *Social*, or *Economic*, *Environmental*.

For indicator values calculated for each sector, firstly, you have to select your sector of interest. The values of the indicators will be displayed for the selected sector.

- Visualising time line graphs can be done by going to the *Economic* sections of the *Indicators* tab. Select on your sector of interest and click on the graph icons  behind the names of indicators.



- Visualising choropleth maps can be done by going to the section ?? by clicking the map icons under the interested indicators. In general, you need to adjust the color legend to show best the choropleth map. See section Legend editor to know how to adjust the color legend. The choropleth maps will be available in the next version.

- Visualising detailed indicator maps can be done by going to the *Environmental* sections of the *Indicators* tab and clicking on the *Show map* button behind the name of the indicator.



All spatial indicators can be stored in log maps and as animations. All other indicator results can be written to Excel. How to writing information to Excel and how to create log maps and animations is described in section 2.3.4 Running a simulation.

How to compare indicators over time and between scenarios is described in 2.3.6 Analysing results.

The indicators will be described in the next version.

2.3.6 Analysing results

Analysing spatial results


In order to analyse spatial results (maps) more carefully it is often helpful to analyse them pixel by pixel or to compare only the land use type you are interested in.

You have created and saved maps with ten year intervals. Also the scenarios have been run and result maps have been saved with the same 10 year intervals.

To investigate these maps you will use the **MAP COMPARISON KIT**, abbreviated to **MCK**. This is a tool that contains a multitude of algorithms to compare maps on a pixel by pixel basis.

Short overview of the MCK

An overview of the **MCK** is provided on the next page.



The **MAP COMPARISON KIT** application window consists of the *Menu bar*, the *Toolbar* and the *Work pane*. You can simultaneously open different windows for maps and statistics. Furthermore, it is possible to keep the *Comparison Settings* dialog window opened while working with the tool:

- The *1st Map* window contains the first map to compare/analyse. To change the contents of *Toolbar* the *1st Map* window, choose another map from the drop down list next to the 1-button on the. If the *1st Map* window is not open yet, then you can do so by clicking the 1-button.
- The *2nd Map* window contains the second map to compare/analyse. To change the contents of the *2nd Map* window, choose another map from the combo box next to the 2-button on the *Toolbar*. If the *2nd Map* window is not yet open, then you can do so by clicking the 2-button.
- The *Result map* window contains the result map. This map shows the spatial result of the last performed map comparison. Depending on the selected comparison method the results are presented in a continuous scale or a nominal scale
- The *Result statistics* window contains the statistical results of the last performed map comparison.
- The *Comparison settings* dialog window allows setting and viewing the settings belonging to the active comparison method.

Comparing different years of one scenario

First we will analyse how the baseline changes over time:

- Go to the *Analysis* tab on the left hand side of the *Main window*.
- Press the *Start Map Comparison Kit* button on the right hand side of the window.

Now you can import the logged maps. You will find the logged maps (*.rst) of the baseline scenario in the folder of \Simulations\Log by default or in the specific folder that you defined in section Log maps.

- Go to the option *Log file...* in the *Options menu*.
- Select the logged maps that you want to analysis and open them: *2000landuse.rst* and *2030landuse.rst*. Automatically the first map that you imported will appear on the map, and it shows the land use for 2000. With the drop down lists in the menu bar you can select which maps is *Map 1* and *Map 2* to compare. Select the 2000 land use map as *Map 1* and the 2030 land use map as *Map 2*.
- Choose the *Per category* in the *Comparison algorithm* window by clicking the *Algorithm* button on the *Toolbar*. Now to choose which land use you want to investigate, click the *Parameters* button on the *Toolbar* and choose *Agriculture* land use. Now the *Result map* will show you 4 options: *in none of the maps*, *in both maps*, *only in map 1 and not in map 2* and *only in map 2 and not in map 1*.


Besides the land use map, you can also analyse other categorical maps in the same way. To do this, select another type of categorical map (e.g. detailed land use, abandoned land, or another indicator) from the drop down list in the *Toolbar* and repeat the steps above.

- If you are interested in looking at the statistical information regarding the changes; go to the option *Result statistic* in the *Options* menu or press the *Statistics* button in the *Toolbar*.

Numerical maps, like the crop area maps that show a percentage of crop area per cell, can be compared using measures that can be found under the *Compare numerical maps* in the *Comparison Algorithm* window.

Select the crop area maps (or any other numerical map) in the drop down list in the *Toolbar*.

- Select *Comparison Algorithm – Compare numerical maps – Cell by cell – b-a*.
- Investigate the changes in crop area of different crops over time.



In this exercise you have investigated the actual land use change over one simulation. A more interesting investigation would be to compare the results of two different scenarios. This you will do next.

Comparing scenarios

The simulation that you used until now, the baseline scenario, represents an extrapolation of observed historic developments combined with expected future developments. You can say it

shows a 'business as usual' scenario, it incorporates the processes as they are observed in the past and expected for the future. However, the full power of a spatial decision support system lies not in this baseline scenario but in investigating different scenarios and analysis of scenarios and effects of policy measures. Hence it helps you to answer "what if. . . ." type of questions.

In this exercise you will compare an alternative scenario with the baseline scenario. For this we will again use the **MAP COMPARISON KIT**.

First we will import an alternative scenario.

- To incorporate the logged maps for the alternative scenario, go to the option *Log file...* in the *Options menu*. Press the *Import...* button on the right hand side of the *Edit Log file* window and select the **.rst* file type and select the logged maps with your scenario of choice.
- Press the *OK* Button.

Instead of comparing the start and end map of one simulation you now want to investigate the difference between two simulations. We will again do this per category.

- In the **MCK** select the baseline result in 2030 as *Map 1* and the alternative scenario result in 2030 as *Map 2*.
- Now you can investigate the categorical maps in more detail. To do so choose the *Per category* in the *Comparison algorithm* window by clicking the *Algorithm* button on the *Toolbar* and select the land uses you are interested in.

Summary

In the final section of this section you have analysed different results maps of the **WAIKATO SDSS** system. You have compared results from different years within a scenario as well as results of a certain year between scenarios. For this you have used the **MCK** functionality to compare categorical maps on a cell by cell basis, to compare numerical maps on a cell by cell basis and to show overall statistics.

2.4 Modeller interface


This section deals primarily with the interaction between the *Modeller* and the software. The modeller can have more detailed access to the underlying models of the system diagram to update data and parameters and to check the outputs. For details about the model, we refer to the accompanying *Model description* reports of **WAIKATO SDSS**.

Only a global overview of the model itself and the features which are not directly linked to the model description will be described in this user manual.

Detailed information about how to update data and parameters through the modeller user interface is given per individual model in section 2.4.5. Notice that setting the parameters is part of the calibration of the system. Changing the parameter settings can have a major impact on the behaviour of the system. If you do not have a good understanding of the individual models, we advice you to use the default settings.

2.4.1 Overview of the system diagram

The *Modeller* finds his way through the user interface by going to the *Parameters* part of the *Main Window* that can be found under *Drivers*. When clicking on *Parameters* the system diagram of the integrated model becomes visible on the right hand side of the *Main window*.



The system diagram in the *Content pane* is the most essential feature of the user interface for modeller. It shows an overview of the structure of the integrated models at the most synthetic level and enables access to the details of the model not only at this level but also at lower levels. You should learn to use it as a graphical explorer of the model. You can change neither the model structure, nor its graphical representation.

The **WAIKATO SDSS** system has been implemented by means of the Decision Support System Generator **GEONAMICA®**. **GEONAMICA®** models consist of *Model Building Blocks* (MBB's) that contain the code and/or data required to calculate and execute mathematical operations varying from a single operation, such as the sum of two numbers, to a complex set of interlinked operations (set of mathematical equations). Model Building Blocks are graphically represented in the user interface by means of a rectangle with the name of the MBB in it. They are connected to one another by means of *MBB-Connectors*.

The **WAIKATO SDSS** MBBs are structured by 4 spatial levels: NZ & World, Region, District and Local level. The MBBs incorporated in **WAIKATO SDSS** are:

- Climate change scenarios

- Hydrology
- Water quality
- Economics
- Demography
- Dairying
- Terrestrial biodiversity
- Land use
- Spatial indicators

The representation of the system diagram in the *Main window* has been created with the help of the following basic elements: *Model Building Blocks*, *MBB-Connectors*, *Connections*, and *MBB-Dialog windows*.

2.4.2 Model Building Blocks (MBB)

Model Building Blocks are represented in the system diagrams of the *Content pane* by means of a rectangle with the name of the MBB printed in it.




An active Model Building Block is represented in black. When the mouse moves over such block its colours are inverted. Next, if you click in it, a dialog window will be open. This dialog window is the user interface of the MBB. It has the double function to receive the user inputs and to display the model outputs.

2.4.3 Connectors and Connections

Variable and parameter values can be passed from one MBB to the other via *Connections*, or *Pipes*. MBB's will dispense variable or parameter values with the rest of the model via *Out-connectors*, and will take-in information from other MBB's via *In-connectors*.

The actual data exchange between MBB's is possible via a *Connection* (or Pipe) between an Out-connector of the issuing block and the In-connector of the receiving block. For each variable or parameter value that is exchanged, a connection is displayed in the diagram.

Symbols	Connector
	In-Connector
	Out-Connector

2.4.4 Dialog windows

Each MBB has a Dialog window associated with it. It is the vehicle that permits the interactive exchange of information between the user and the Model Building Block: the MBB will communicate the results (outputs) of its numerical operations to the user and it will take in the data entered (inputs) by the user that are required for the execution of the MBB. It concerns data that are internal to the MBB which it does not get from other MBB's via its In-Connectors.

Clicking on each of the model names gives you access to the underlying model. A dialog window that pops-up is organised in such a way that the (external) input, parameters, and output can be found and adapted on the left or top part of the window, while the output can be found at the right or bottom.

In **WAIKATO SDSS** system, the inputs and outputs are organised by *map*, *map file*, *graph*, *single value* and *table*. The user can find the detailed description about how to edit inputs and display outputs by the categories of *map*, *map file*, *graph*, *single value* and *table* in 2.2.2.

Information on all of the underlying models and their data and parameters can be found in the Model description reports of the **WAIKATO SDSS** system. Section 2.4.5 Individual model components will describe the user interface of each individual model components.

2.4.5 Individual model components

Land use change model

Land use classes

Land use is classified in categories, some of which are land uses modelled dynamically and some of which remain static in the model. Thus, a distinction is made in the model between dynamic and non-dynamic land uses: the dynamic land uses are called *Functions* or *Vacant* land uses.

- *Vacant* states finally are classes that are only changing as a result of other land use dynamics. Computationally at least one vacant state is required. Typically abandoned land or natural land use types are modelled as vacant state, since they are literally vacant for other land uses or the result of the disappearance of other land use functions.
- *Functions* are land use classes that are actively modelled, like residential or industry & commerce. Functions change dynamically as the result of the local and the regional dynamics.

The non-dynamic land uses are called *Features*. Features are land use classes that are not supposed to change in the simulation, like water bodies or airports. They will not expand, will not disappear, and will not change location due to expansion of other land uses or any other dynamics in the model. Yet, they influence the dynamics of the *Functions*, and thus influence their location. For example a *Function* ‘Tourism’ would be influenced (expressed in a spatial interaction rule) by the occurrence of the *Feature* ‘Beach’, due to the simple fact that tourists tend to recreate near the sea at the beach.

In the **WAIKATO SDSS** application the following land uses are modelled:

Land use	States
Marine	Vacant
Bare Surfaces	Vacant
Indigenous Vegetation	Vacant
Other Exotic Vegetation	Vacant
Wetland	Vacant
Residential-Lifestyle Blocks	Function
Residential-Low Density	Function
Residential-Medium to High Density	Function
Commercial	Function
Community Services	Function
Aquaculture	Function
Horticulture	Function
Biofuel Cropping	Function
Vegetable Cropping	Function
Other Cropping	Function
Dairy Farming	Function


Sheep, Beef or Deer Farming	Function
Other Agriculture	Function
Forestry	Function
Manufacturing	Function
Utilities	Feature
Mines and Quarries	Feature
Urban Parks and Recreation	Feature
Fresh Water	Feature
Airports	Feature
Land Outside Study Area	Feature
Marine Outside Study Area	Feature

In **WAIKATO SDSS** system, the land use demand comes from the Economic model and Demography model.

Overview

The *Land use change model* dialog window opens after clicking on the *Land use* MBB box in the system diagram under *Drivers->Parameters* at the Local level.

The *Land use change model* dialog window has been grouped in so-called *Vertical Group*: Land use parameters, Total potential parameters, Neighbourhood parameters, Zoning parameters, Suitability parameters and Accessibility parameters.




The user can expand or collapse one of the *Vertical Groups* by right clicking on it. The system allows you to open the *Vertical Groups* as many as you want. When you right click on one of the *Vertical Groups*, the *Context* menu opens, which controls how *Vertical Groups* are arranged on the desktop. The list below summarizes the *Context menu* commands. While the command is selected, the option of group on the *Context* menu is preceded with a mark.



Use this button	To:
Expand all	Expand all the Vertical Groups in the land use model parameters dialog window
Collapse all	Close all the Vertical Groups in the land use model parameters dialog window
Land use parameters	Open or close the Land use parameters group in the land use model parameters dialog window
Total potential parameters	Open or close the Total potential parameters group in the land use model parameters dialog window
Neighbourhood parameters	Open or close the Neighbourhood parameters group in the land use model parameters dialog window

Use this button	To:
Zoning parameters	Open or close the Zoning parameters group in the land use model parameters dialog window
Suitability parameters	Open or close the Suitability parameters group in the land use model parameters dialog window
Accessibility parameters	Open or close the Accessibility parameters group in the land use model parameters dialog window

Land use parameters



The user is able to view, edit land use maps via the Land use parameters group. The land use parameters are structured by *Input* and *Output* components which are allocated on the left side and right side of the window, respectively.

The user can view or edit the initial land use map by using the *Edit initial land use map* button in the *Input* section. A *Map window* of *Initial land use map* opens immediately after pressing the *Edit initial land use map* button. Section *Map window* describes how to view and edit the land use map in the *Map window*.

Based on the initial land use map for the start year, the system allows the user to add the land use changes with specific time by adding the land use change map file. The description about how to *Add* or *Delete* the map files is available in section *Map file*.

Move the mouse over your interest land use changes on the map file list and click on it, this land use change will be highlighted, then press the *View current land use map and selected changes* button on the bottom of *Input* section, a *Map window* displays which is a overlay of the land use map for the current simulation and the selected land use changes.

The user can view the land use map of the current simulation year by pressing the *View land use map* button in the *Output* section.

In the future version of system, the user can view land use summary in your interested region. Go to *Summary* part in the *Output* section, select the interested region on the dropdown list of *Region*, and then press the *View land use summary* button on the bottom. The land use summary for the specific region opens. In this version of **WAIKATO SDSS**, the *View land use summary* function is not available.

Total potential parameters

The user is able to specify the details of the algorithms used to calculate the total potentials in the land use model. The algorithms can be specified separately for the so-called *vacant* land uses (named unconstrained states) and for the *function* land uses (constrained states).

The total potential for the *vacant* and the *function* states combines the effect of the *neighbourhood*, *suitability*, *zoning* and *accessibility*. The user can find the detailed description of interface of their parameters in the following sections. The neighbourhood effect is given a stochastic perturbation to simulate the effect of unpredictable occurrences. The extend of this perturbation can be controller with the *Random coefficient*.

The model is very sensitive to the total potential algorithms. Hence, changing them may have drastic effects on the land use change dynamics. It is better not to tinker with the total algorithms unless you have gained a lot of experience with the model.




The system enables the user to enter the *Random coefficient* in the *Input* section under the *Total potential parameters* group. As described early, the *Random coefficient* is a parameter that controls the stochastic perturbation performed on the *Neighbourhood* effect. The value of this parameter must be not less than 0. According to our experience, rang of (0, 2) is the recommended value. A value of 0 means no perturbation.

The system allows you to view the total potential map for you interested vacant or function land uses. Select the vacant or function land use on the *Land use vacant/function* dropdown list, and then press the *View total potential map* button. A *Map window* of the total potential map for the selected land use will open immediately. A potential map displays the transition potential of a cell for changing to the land use specified. On the basis of the transition potentials the model decides which land use will be allocated to each cell in the next simulation step. Colours in the total potential map range from red to green. Cells in red are not attractive for the function. In contrast, the green cells are. In the legend of the potential map you will find next to the colour symbol two numbers. The figure to the left is the upper limit of the category. The figure to the left is the lower limit of this category taken in by the land use function mapped.


Neighbourhood parameters

In the *Land use* model, first and most important are the *Neighbourhood influence rules*. They represent the dynamic element of the Land use model.




The *Neighbourhood influence rules* are accessible via the *Neighbourhood parameters* Vertical group in the *Land use* MBB. The *Neighbourhood influence parameters* window opens after you click the *Influence rules...* button. It is divided by 3 panes: Overview pane, Graph pane and List pane.

The *Neighbourhood influence parameters* dialog window displays the influence land uses have on each other, as used by the land use model. The likeliness that a certain land use will stay in a certain cell is, among others, dependant on the land uses that occupy the area around that cell. For example, people do not like to live close to an industrial area, so industry will have a negative influence on housing that decays as the distance between the two places increases.




The influence that a certain land use has on another land use (or itself) is described as a function of the distance between two cells (so-called a spline), which is made up of a series of points that are connected in a certain manner. An example of such a function is shown in the figure above, where the points are connected by linear interpolation. In this graph, the distance runs along the horizontal axis and the vertical axis displays the influence that land use A has on land use B. We see that, when land use A and B are situated at a distance of 1 (cells), land use B has a positive effect on land use A of approximately 5.





We will now describe all the functionality of the *Neighbourhood influence parameters* dialog window, as indicated in the figure above.

1. *Influence table*. This displays the influences of each land use on each function land use: *From... To...* Some of the cells in this table show what the spline that describes the corresponding influence looks like. If a spline is flat (0 influence for all distances), it is not displayed in the table. Click on a cell in the table to select that influence. The spline that describes that influence is displayed on the right side of the dialog.
2. *Auto save changes*. If this is checked, the changes that you make to the spline on the right side of the dialog will automatically be saved when you select another cell in the influence table or when you press the exit button. If the *Auto save changes* is not selected, a window will pop-up and ask you whether or not to save the change that you made when you activate another rule.




3. *Spline graph*. This displays the graph of the neighbourhood rule that is currently selected in the influence table. The user can find the name of this rule above the graph. The graph represents the two-dimensional relation. The x-axis is the *Distance* by cells, and the y-axis is the *Value* of influence. The points of the spline are displayed as small circles, which are connected by a blue line.

- Points in the graph can be moved by dragging them with the mouse. Clicking on a point will, it turns red. Holding Ctrl or Shift and clicking on a point will (de)select multiple points. If you hold Ctrl or Shift, you can also make a selection rectangle by dragging with you mouse. All points within the selection rectangle will be added to the selection when you release the left mouse button. By selecting several points, you can move all of them without affecting their mutual relation, with the constraint that points cannot be dragged outside the graph area.
- Right clicking on a point in the graph will open a small dialog that allows you to view or enter the coordinates of a point, as shown in the figure below. At the bottom of this *Edit point* dialog window, a note for the range of X values is given. You can only enter values for X that fall in this range, otherwise a message reminds you again of this range.



4. *Display options*. This opens the *Spline display options* dialog window as shown in the figure below. In this dialog the extent of the graph can be altered.

- In this version, the system allows user to determine the range of the x- and y-axis enter the lower and upper bounds in the text boxes.
- When the *Display grid* check box is checked, grids are drawn in the graph window. When the *Display ticks* check box is checked, vertical lines at all possible cell distances are drawn in the graph window.




5. *Save*. This will save the changes you have made to the current spline by pressing the *Save* button which is available only after it is changed.


6. *Reset*. This will undo the changes you have made to the current spline, by resetting it to its last saved state. The *Reset* button is available only after a spline is changed.

7. *Values list*. The system provides a table with the coordinate pairs for all discrete cell distances on the right hand side of the window.

The value list is not editable. The relation can be edited in the graph only. Changes made are immediately visible in the spline graph and on the value list as well.



Computed from the *Neighbourhood influence rules*, there are two types of outputs for each function land use under the *Neighbourhood parameters* group: the *Inertia map* and the *Neighbourhood effect map*.




The inertia map shows the inertia of a function land use. In the *Output* section, select the function land use of your interest from the dropdown list of *Land use function*. Press the *View inertia map* button, the *Map window* of the selected function land use opens. Colours in the inertia map range from green to red. Cells in green have very high inertia for the specific function land use. In contrast, the red cells have not.

The neighbourhood influence rules describe the effect of one land use on another at each distance in the neighbourhood. These influences are accumulated to produce the neighbourhood effect in each cell for each land use function. The neighbourhood effect map shows this neighbourhood effect for the selected land use function for each cell. Press the *View neighbourhood effect map* button, a *Map window* of *Neighbourhood effect* for specific land use function opens. The description of *Map window* is available in the section *Map window*.

Zoning parameters


The zoning or institutional suitability is characterized by one map for each land use function. It is a composite measure based planning documents available from the national or regional planning authorities and containing among others ecologically valuable and protected natural areas, protected cultural landscapes, buffer areas, etc.



This dialog under the *Zoning* parameters group is divided into two parts: a part on the left hand side is specific for each zoning map – corresponding to a land use function; and a part that is common for all zoning maps.

In the left hand part, the user can select your interested land use function on the dropdown list. As mentioned in section Policy measures, the restrictions can be relieved over time. The different classes in zoning maps are: Allowed, Allowed after Start period 1, Allowed after Start period 2 and Establishment prohibited. The respective four moments for these classes are: the start year of the simulation, the first planning period, and the second planning period and never. You can enter the dates and time for the *Start period 1* and *Start period 2* in the text boxes.

After you select the land use function of your interest and determine the start of the zoning periods, you can import the zoning maps that you have created in the **OVERLAY-TOOL**. An *Import zoning map* for a “specific land use function” opens where you can select the corresponding zoning map.



In a zoning map, for each cell, four zoning states are possible:




- 0: the activity is already present in the cell and / or is allowed from the first planning period onwards (green cell);
- 1: the activity is allowed in the cell from the second planning period onwards (yellow cell);
- 2: the activity is allowed in the cell from the third planning period onwards (orange cell);
- 3: the activity is never allowed in the cell (results in a red cell on the map).

You can edit zoning maps by pressing the *Edit zoning map* button on the left hand side of the dialog. A *Map window* showing the *Zoning map* for “specific land use function” opens. With the *Grid tools* in this *Map window*, it is possible to assign specific zoning statuses to individual cells.

In the right hand part, *Zoning anticipations (for all land uses)*, the system allows you to configure the anticipation to changes in the zoning status. You can specify the type of anticipation (linear (by default) and S-shape) as well as the size of this effect. A value smaller than 1, but larger than 0, will cause a more delayed transition and a value larger than 1 will cause an earlier transition. This zoning anticipation acknowledges that before zoning measures are released; already the first developments can start.

Suitability parameters



Suitability is represented in the model by one map for each vacant land use or function land use. Values on the suitability map quantify the effect that physical characteristics of the land have on the possible future occurrence of land uses. The suitability maps could be created with the help of the **OVERLAY-TOOL**. You can select your interested land use on the dropdown list of *Land use vacant/function*.

The path of the suitability map file for the first date and time is displayed by default when you open the system. The system allows the user to add the suitability map for specific land use with specific time by clicking on the *Add* and *Del* button. The description about how to add or delete the map files is available in section Map file.

The user can view or edit the suitability map by clicking on the *Edit* button. With the opened *Suitability map* for “specific land use” Map window, it is possible to change the suitability value of individual cells. A higher value indicates a higher suitability. Suitability is displayed in the map in colours varying from cyan to red, representing values between 0 (not suitable) and 10 (perfectly suitable). Before you add the suitability map to the system, you have to ensure that the values on the map are integer values.

The system provides the opportunity to set up the maximum suitability (for all land uses) by enter a value of the range of (0, 255) in the *text* box. This maximum suitability value should be the highest value on any suitability map in the **WAIKATO SDSS** system. In general, if the suitability map is created in in **OVERLAY-TOOL**, it can be used directly in **WAIKATO SDSS** system with a maximum suitability value of 10.

Accessibility parameters

The accessibility for each land use function is calculated as a function of the distance to the nearest road network. It represents how easy an activity can fulfil its needs for transportation from a particular cell. It accounts for: the distance of the cell to the nearest link or node, the quality of that link, and the needs for transportation of the particular activity or land use function.

Accessibility parameters

Inputs

Land use: Agriculture

Land use is build up

Land use is impassible

Implicit accessibility for build-up areas: 0.2

Implicit accessibility for non-build-up areas: 1

Infrastructure type	Distance decay	Weight
Motorway	-10	0.8
Dual carriageway road	-8	1
Other road	5	1
Car ferry	1	0.2

Outputs

Land use function: Agriculture

View accessibility map

The system allows you to specify the accessibility parameters used for the calculation of the accessibility maps for each land use class by following steps:

- Select the land use of interest in the dropdown list *Land use* in the *Inputs* section.
- Select the *check box* in front of *Land use is build up* if the particular land use in the model is contained in the set of urbanised land uses (for example residential land use). Select the *check box* in front of *Land use is impassible* if the particular land use in the model is impassible for other land uses (for example water).
- Set the implicit accessibility parameters per land use function. The *Implicit accessibility* values range from 0 to 1. Enter the *Implicit accessibility* parameter for the particular land use on a build-up area in the text box after *Implicit accessibility for build-up areas*. Enter the *Implicit accessibility* parameter for the particular land use on a non build-up area in the *text box* after *Implicit accessibility for non-build-up areas*. The text boxes of *Implicit accessibility parameters* are only available when one of the land use functions in the model is currently selected on the dropdown list.
- Specify the distance decay and weight parameters per land use function. The parameter table allows you to set the *Distance decay* for the effect of each *Infrastructure type* of the network on each land use function and its *Weight*. The distance decay is the number of cells after which the effect is halved (for positive decays) or doubled (for negative decays). The weight determines the relative importance of the infrastructure element for the particular land use function. The distance decay can be positive – for example, industries like to be near highways – or negative – for example, natural areas are preferably not located close to highways. With positive decays this is then the maximum value and with negative decays the minimum value. To turn off the accessibility effect of a specific land use, you can set its weight to zero.


In order to visualize the accessibility map of a land use function, it is imperative that the simulation has been initialised (see section Init) or the accessibility has been computed (see section Step). Use the *Step* command to compute the new accessibility maps after the network has been changed (see section How to view and adapt the road network?)

) or when accessibility parameters have been changed.

The user can select the land use function of interest from the dropdown list of *Land use function* in the *Outputs* section. And then press the *View accessibility map* button to display the accessibility map of the specific land use function in the background of the network map. The *Accessibility for specific land use Map* window opens after pressing the *View accessibility map* button. Accessibility is expressed in the range 0 to 1 and is displayed in colours varying from red to green: red meaning low accessibility (0) and green meaning high accessibility (1).

Economic model

The *Economic model* dialog window opens when you click on the *Economics* MBB box in the system diagram under *Drivers->Parameters* at the Region level.



The *Economic model* dialog window is structured by 6 tabs: *Sector-land use correspondence*, *Consumption*, *Demand*, *Land use constraint*, *Supply* and *Indicators*.


Scroll bar and slider in the table



The *Scroll bar* is located the left top part of the dialog window. Four scroll buttons are positioned that enable the user to arrange the tabs of the dialog window in an easier way to work when the 6 tabs are not all displayed in the *Economic model* dialog window.

Use this command	To...
⏪	Move to the left end tab
⏩	Move tabs to left
⏴	Move tabs to right
⏵	Move to the right end tab

The *Economic model* dialog window is mainly consists of tables. Some of the headings of the tables are not displayed completely. In general, the complete heading could be highlighted by moving the mouse pointer over the heading.



The slider can be used to resize the width of columns in the table. Move the mouse pointer to the border of two columns that you want to enlarge. Then press the left button of the mouse and drag to resize.

Parameters
Sector to land use correspondence

Sector / Function	Resid...	R...	R...	C...	C...	Aq...	Ho...	Bio...	Ve...	Ot...	Dai...	She...
Horticulture and fruit growing	0	0	0	0	0	0	0	0.1...	0	0.8...	0	0
Livestock and cropping farming	0	0	0	0	0	0	0	0	0	0.0...	0	0.9...
Dairy cattle farming	0	0	0	0	0	0	0	0	0	0	1	0
Other farming	0	0	0	0	0	0	0	0	0	0.0...	0	0.9...
Services to agriculture, hunting and forestry	0	0	0	1	0	0	0	0	0	0	0	0
Forestry and logging	0	0	0	0	0	0	0	0	0	0	0	0

Apply Reset

Sector – land use correspondence

The *Sector – land use correspondence* tab is structured by the *Parameters* section and the *Output* section.

Economic model
Sector - land use correspondence Consumption Demand Land use constraint Supply

Parameters
Sector to land use correspondence

Sector / Function	Residential - Lifestyle Blo...	R	C	A	H	B	V	O	D	S	O	F	M
Horticulture and fruit growing	0	0	0	0	0	0	0	0	0	0	0	0	0
Livestock and cropping farming	0	0	0	0	0	0	0	0	0	0	0	0	0
Dairy cattle farming	0	0	0	0	0	0	0	0	0	1	0	0	0
Other farming	0	0	0	0	0	0	0	0	0	0	0	0	0
Services to agriculture, hunting and forestry	0	0	1	0	0	0	0	0	0	0	0	0	0
Forestry and logging	0	0	0	0	0	0	0	0	0	0	0	1	0
Fishing	0	0	0	0	0	0	0	0	0	0	0	0	0

Apply Reset

Output
Inverse correspondence

S.	R.	R...	R...	C...	Co...	Aq...	Hor...	Bio...	Ved...	Oth...	Dair...	She...	Othe...	Fore...	Man...
R.	0	0	0	0...	0	0	0	0	0	0	0	0	0	0	0
A.	0	0	0	0...	0	0	0	0	0	0	0	0	0	0	0
R.	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
W.	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
A.	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
C.	0	0	0	0...	0	0	0	0	0	0	0	0	0	0	0
F.	0	0	0	0...	0	0	0	0	0	0	0	0	0	0	0
I.	0	0	0	0...	0	0	0	0	0	0	0	0	0	0	0

On the top of the *Sector – land use correspondence* tab, a default *Sector to land use correspondence* table is shown, representing the land use functions of the land use model in the rows and the sectors in the columns. Here we specify the extend to which each land use function contributes to each sector. The ratio coefficients in the *Sector to land use correspondence* table are used to convert land use demand per sector to land use demand per function.

You can view or adjust the relation between land use functions and sectors by clicking on the corresponding cell in the table, and adjusting the ratio coefficient. Note that the values are fractions and that all fraction for one function should add up to exactly 0 or 1.

Press the *Apply* button under the *Sector to land use correspondence* table to confirm the modification. One system message window will pop up to remind you to reset the coefficients if the values for each function don't sum to 0 or 1. The system enables you to undo changes in coefficients you have made to its last applied state by means of the *Reset* button. The *Apply* button and *Reset* button are only active after the change has been made.

Parameters
Sector to land use correspondence

Sector / Function	Residential - Lifestyle Blo...	R	C...	C.	A.	H.	B.	V...	O.	D...	S...	O...	F...	M
Horticulture and fruit gro...		0	0	0	0	0	1...	0	0...	0	0	0	0	0
Livestock and cropping far...		0	0	0	0	0	0	0	0	1...	0	0...	0...	0
Dairy cattle farming		0	0	0	0	0	0	0	0	0	1	0	0	0
Other farming		0	0	0	0	0	0	0	0	1...	0	0...	0...	0
Services to agriculture, hu...		0.1	0	0.9	0	0	0	0	0	0	0	0	0	0
Forestry and logging		0	0	0	0	0	0	0	0	0	0	0	0	1

Apply Reset

On the bottom of the *Sector – land use correspondence* tab, you find the *Inverse correspondence* table representing the land use functions of the land use model in the rows and the sectors in the columns, in which the outputs of the extend to which each sector contributes to each land use function are shown. The ratio coefficients in the *Inverse correspondence* table will be used to convert land use demand per function at the local level to land use demand per sector at the regional level. All sector totals should add up to exactly 0 or 1 again.

The values of the *Inverse correspondence* table are updated over time. The user can observe the change of the *Inverse correspondence* table after taking one step simulation if the change of the ratio coefficients has been made in the *Sector to land use correspondence* table.

Consumption

Economic model

Sector - land use correspondence Consumption Den

Input

Sector	Initial household consumption (min...
Horticulture and fruit growing	13.0684
Livestock and cropping farming	4.31188
Dairy cattle farming	0.82791
Other farming	5.20677
Services to agriculture, hunti...	1.89713
Forestry and logging	4.12501

Parameters

Consumption scalars

Age	Males	Females
0 - 4 years	0.825	0.8177
5 - 9 years	0.8732	0.8708
10 - 14 years	0.8828	0.8828
15 - 19 years	0.9021	0.919
20 - 24 years	1.1168	1.1795

Output

Sector	Current household consumption (...)
Horticulture and fruit growing	13.0684
Livestock and cropping farming	4.31188

The *Consumption* tab is structured by *Input*, *Parameters* and *Output* section. You can review and edit the inputs in the table of *Input* section. This represents the initial household consumption per sector for the start year of the simulation.

In the middle of the *Consumption* tab, you can review or edit the consumption scalars per age-sex cohort in the table of the *Parameters* section. The consumption scalars are used to convert the outputs from the Demography model (see section Demography model) to the average person equivalent.

On the bottom of the *Consumption* tab, it features the output of the current household consumption for each sector. The values of the *Current household consumption* table are updated over time. The user can observe the changes in the *Current household consumption* table after taking one step. However, in order to have the consistent parameter values over time, it is suggested to reset the simulation before running it.

Demand

The *Demand* tab is split in 3 parts by the sections: *Input*, *Parameters* and *Output* section.

Economic model

Sector - land use correspondence Consumption Demand Land use constraint Supply Indicators

Input

Time: 2004-Jan-01 Add time Delete time

Sector	International exports (mln\$...)	Interregional exports (mln\$...)	Gross fixed capital formati...	Changes in inventories (ml...)
Horticulture and fruit growing	86.8835	0.223444	0.241278	-3.12064
Livestock and cropping far...	28.9126	39.1873	0.946384	-40.1217
Dairy cattle farming	0.823411	828.104	0.672205	-339.45
Other farming	17.6921	1.23824	0.0768642	34.0682
Services to agriculture, hun...	0	6.18163	12.5794	-62.0964

Parameters

Inverse Leontief matrix

Sector / Sec...	Horticulture ...	Livestock an...	Dairy cattle ...	Other farming	Services to ...	Forestry an...	Fishing	Mining and ...	Oil and q
Horticulture ...	1.01294	0.0124377	0.0192297	0.00756484	0.0103621	0.0109534	0.00112466	0.000580134	
Livestock an...	0.0354288	1.16261	0.0502031	0.0512455	0.0437754	0.0243183	0.0112002	0.00518878	
Dairy cattle ...	0.00785599	0.0257647	1.01759	0.0105521	0.0100943	0.00397852	0.0026695	0.00292351	
Other farming	0.00966101	0.0138343	0.0128085	1.01409	0.0113277	0.00281665	0.000856083	0.00031695	
Services to ...	0.117452	0.105247	0.0610444	0.0776804	1.11416	0.127541	0.0107044	0.00308492	

Output

Sector	Final demand (mln\$2004)	Output (mln\$2004)
Horticulture and fruit growing		97.296
Livestock and cropping farming		33.2365
Dairy cattle farming		490.978
Other farming		58.2822
Services to agriculture, hunting and trapping		-41.4382
Forestry and logging		16.6642
Fishing		28.5135

In the *Input* table of the *Demand* tab, the system allows the user to edit the input of *International exports*, *Interregional exports*, *Gross fixed capital formation* and *Changes in inventories* for a specific year.

Input

Time: 2004-Jan-01 Add time Delete time

Sector	International exports ...	Interregional exports ...	Gross fixed capital for...	Changes in inventorie...
2004-Jan-01				
2006-Jan-01				
2011-Jan-01				
Horticulture and fruit growing	86.8835	0.223444	0.241278	-3.12064
Livestock and cropping farming	28.9126	39.1873	0.946384	-40.1217
Dairy cattle farming	0.823411	828.104	0.672205	-339.45
Other farming	17.6921	1.23824	0.0768642	34.0682
Services to agriculture, hunting and trapping	0	6.18163	12.5794	-62.0964

You can select a specific year from the drop down list *Time*. The table then shows the input for this selected year. You can edit the values per specific year.

The system enables the user to edit the time list by using the *Add time* function and the *Delete time* function. The *Enter data and time* dialog window opens when the *Add time* button is clicked. You can enter the specific time in the text box of the *Enter data and time* dialog window.

Enter date and time

2010-Jan-01 00:00:00

OK Cancel

After you press *OK*, the specific time will be displayed immediately on the drop down list *Time*. The system takes the interpolated value for the new added time on the basis of the values for the specific years on the drop down list.

Sector	International exports ...	Interregional exports ...	Gross fixed capital for...	Changes in inventorie...
2004-Jan-01				
2006-Jan-01				
2010-Jan-01				
Horticulture	85.0052	0.346768	0.321958	4.73229
Livestock	1.11242	49.3706	1.87762	-6.71156
Dairy	1.61671	1138.94	1.62832	-466.606
Other	12.7187	1.61733	0.151334	40.1189
2031-Jan-01				
Services to agricultur...	0	2.9073	12.5094	-36.7092

You can easily delete the table for one specific year by selecting this specific year on the drop down list and press the *Delete time* button next to the *Add time* button. A message window opens. Press the *Yes* button of the message window to carry out the action of deleting table for the selected year. Press the *No* button of the message window to cancel the action of deleting table for the selected year.

In the middle of the *Demand* tab, the *Inverse Leontief matrix* from sector to sector is editable in the *Parameters* section.

On the bottom of the *Demand* tab, the output of the *Demand* module includes the *Final demand* and the *Output* in mln \$ (2004) per sector. The outputs are updated dynamically over the simulation period.

- The *Final demand* of the *Demand* tab is calculated on the basis of *International exports*, *Interregional exports*, *Gross fixed capital formation*, *Changes in inventories* and the *Current household consumption* in the *Consumption* tab.
- The *Output* per sector of the *Demand* tab is the output of all sectors which are caused by the *Final demand* for this specific sector

Land use constraint

After the *Final demand* and *Output* of the *Demand* module are calculated, the land use demand estimates in the *Land use model* are taken into account in the *Land use constraint* tab. This *Land use constraint* tab is split into *Parameters* section and *Output* section.

On the top of the *Land use constraint* tab, you can view and edit the *Eco-efficiency* per sector. The *Eco-efficiency* is used to convert the mln \$ 2004 per Sector and vice versa.

Sector	Eco-efficiency (ha / mln\$2004)
Horticulture and fruit growing	41.4083
Livestock and cropping farming	944.473
Dairy cattle farming	336.394
Other farming	169.037
Services to agriculture, hunting and trapping	0.171655
Forestry and logging	939.161

Sector	Output corresponding to constr...	Change in output due to land us...
Horticulture and fruit growing	169.821	-8.52651e-014
Livestock and cropping farming	656.984	-0.121709
Dairy cattle farming	1777.91	-0.0713448
Other farming	131.311	-0.0243259
Services to agriculture, hunti...	252.6	-2.84217e-013
Forestry and logging	365.143	-0.0255547

Land use function	Unconstrained land use deman...	Constrained land use demand (ha)
Residential - Lifestyle Blocks	0	61192
Residential - Low Density	0	17408
Residential - Medium to High ...	0	628
Commercial	1236	1236

On the bottom part of the *Land use constraint* tab, two tables are displayed as the outputs which are updated over the simulation period.

- The *Unconstrained land use demand* per land use function is calculated on the basis of the *Output* of the *Demand* tab and the *Eco-efficiency*. The *Unconstrained land use*

demand for Residential land uses, Aquaculture and Biofuel cropping are zero because their land use demand is not calculated in the Economic model.

- The *Constrained land use demand* per land use function is the output which is constrained by the land use demand from the land use model.
- The *Output corresponding to constraint land use* per sector is calculated on the basis of the *Constrained land use demand* and the *Eco-efficiency*.
- The *Change in output due to land use constraint* per sector is the difference between *Output corresponding to constraint land use* and the *Output* of the *Demand* tab.

Supply

The *Supply* tab is split in 3 parts: *Input*, *Parameters* and *Output* section.

Sector / Sec...	Horticulture ...	Livestock an...	Dairy cattle ...	Other farming	Services to ...	Forestry an...
Horticulture ...	0.986907	-0.0145705	-0.0196395	-0.00884451	0	-
Livestock an...	-0.058634	0.627784	-0.0536764	-0.159114	0	-0
Dairy cattle ...	-0.129997	-0.131443	0.504058	-0.134895	0	-
Other farming	-0.0114306	-0.0323294	-0.0139416	0.976074	0	-0.1
Services to ...	-0.0900849	-0.0976367	-0.0453223	-0.0591001	0	-0
Forestry an...	-0.00950649	-0.0110041	-0.00575999	-0.0067468	0	
Fishing	-0.000593029	0.000146568	2.4646e-006	-6.04388e-005	0	0.0
Mining and ...	-0.00420067	-0.00655646	-0.0117097	-0.00810189	0	0.0

Sector	Change in final dema...	Final demand (mln\$2004)	Output (mln\$2004)
Horticulture and f...	0	109.683	183.624
Livestock and cro...	1.42109e-014	45.4026	695.899
Dairy cattle farming	-1.13687e-013	462.19	1730.75
Other farming	0	64.6938	139.698

On the top part of the *Supply* tab, the system allows the user to view and edit the *Ghosh matrix* from sector to sector.

On the bottom part of the *Supply* tab, the user can observed the outputs per sector which are updated over the simulation period.

- The *Change in final demand* per sector is calculated on the basis of the *Change in output due to land use constraint* of the *Land use constraint* tab and the *Ghosh matrix*.
- The *Final demand* per sector is calculated on the basis of the *Final demand* of the *Demand* tab and the *Change in final demand*.
- The *Output* per sector is calculated on the basis of the *Final demand* and the *Inverse Leontief matrix* of the *Demand* tab.

Indicators

The *Indicators* tab is structured by the *Input*, *Parameters* and *Output* sections.

Economic model

Sector - land use correspondence Consumption Demand Land use constraint Supply Indicators

Input

Sector	Initial q...	Initial v...	Initial in...	Initial e...	Initial ...	Initial e...	Initial en...	Initial en...	Initial tot...	Initial ene...	Initial total...
Hortic...	2	89.7864	7.76654	1961	128023	10912.6	0	29437.6	170343	11514.5	80.2488
Livest...	1	288.8	36.487	5583	398908	34002.5	0	91724.6	530772	35878	123.77
Dairy ...	1	891.254	117.289	13355	1.1340...	506902	0	260699	1.91908e...	125366	117.108
Other ...	1	52.5377	10.7242	2142	97771.7	8333.96	0	22481.6	130091	8793.64	32.3158
Servic...	1	131.89	8.92222	2948	179872	92009.9	0	41358.9	316003	20546.3	26.0896
Forest...	1	147.725	13.3587	1896	291030	136883	0	74866.3	506764	33052.9	0

Parameters

Sector	Rate of change in labour force productivity (...)	Rate of change in eco-efficiency (% / year)
Horticulture and fruit growing	0.44	0.5
Livestock and cropping farming	1.66327	0.5
Dairy cattle farming	3.45754	0.5
Other farming	2.25016	0.5
Services to agriculture, hunting and trapping	0.44	0.5
Forestry and logging	1.80023	0.5

Output

Sector	Current...	Current...	Current...	Current...	Current...	Current...	Current ...	Current ...	Current t...	Current e...	Current to...
Hortic...	1.01356	98.4013	8.51173	2120.91	138213	11781.1	0	31780.6	183901	12431	86.6359
Livest...	1.03527	316.696	40.0114	5821.84	430911	36730.4	0	99083.3	573354	38756.3	133.699

On the top of the *Indicators* tab, it shows the *Input* table where you can view and edit the initial values of the indicators per sector for the start year of the simulation. It should be noted that the initial value must be non-negative.

In the *Parameters* table you can view and edit the *Rate of change in labour force productivity* and the *Rate of change in eco-efficiency* per sector.

On the bottom, you can see the output of indicators per sector.

- The first column in the *Output* table is the *Current growth factor* which is calculated on the basis of the *Output* of the *Supply* tab for the current year and the one for the previous year.
- The *Current value added* is calculated on the basis of the *Initial growth factor* and the *Initial value added*.
- The *Current international imports* is calculated on the basis of the *Initial growth factor* and the *Initial international imports*.
- The *Current employment* is calculated on the basis of the *Initial growth factor*, the *Initial employment* and the *Rate of change in labour force productivity*.
- The rest indicators of the *Output* table are calculated on the basis of their initial values, the *Initial growth factor* and the *Rate of change in eco-efficiency*.

Demography model

The *Population data* dialog window opens when you click on the *Demography* MBB box at the regional level in the system diagram under *Drivers->Parameters*.

In this version, the user can view and edit the population by sex-age cohort for the specific years. This is mainly used as input for the Economic model (see section Economic model).

Age	Males	Females
0 - 4 years	13985	13857
5 - 9 years	15232	14422
10 - 14 years	16539	15314
15 - 19 years	15093	15033
20 - 24 years	13320	12728
25 - 29 years	11273	11576
30 - 34 years	12061	13344
35 - 39 years	13989	15531
40 - 44 years	14177	15104
45 - 49 years	13765	14185
50 - 54 years	11677	11867

You can select a specific year in which you are interested on the drop down list *Time*. The table shows the input for this selected year. You can edit the values per year.

The system enables you to edit the time list by using the *Add time* function and the *Delete time* function. Detailed description about how to use these two functions is available in section Demand of the Economic model.

2.5 The WAIKATO SDSS menu system


This section explains the different functions that are available from the **WAIKATO SDSS** menu system. Some **GEONAMICA**[®] functions are not available in **WAIKATO SDSS**. These are greyed out, meaning that they are visible in the menus in a light grey colour, but they do not result in further actions when invoked. Consequently, these functions are not described in detail in this section.

Other functions are only accessible when they are relevant. For instance, the *Stop* command in the *Simulation* menu is only accessible when the simulation is running.

The menus are treated as they appear in the *Menu bar* from left to right and per menu from the top to the bottom. Most commands in this section have already been described in other sections. The user can find more detailed information for these commands through the links in the table.

2.5.1 The File Menu

Use the *File* menu to open and save simulation files, and to exit **WAIKATO SDSS**. **THE WAIKATO SDSS** saves simulation files with a .xml extension attached to the file name.




Use this command	To...	Link
New simulation...	Create a new simulation with Waikato SDSS	Not available in this version
Open simulation...	Open a simulation file stored on a disk	Section Opening a simulation file
Save simulation	Save changes to the current simulation file	Section Save simulation
Save simulation as...	Save a simulation to a disk	Section Save simulation as

Use this command	To...	Link
Close simulation	Close the simulation	
Recent file	Display the names and the paths of the 4 most recently opened simulation files. If you select one of the 4 files, it will be opened	Not available in this version
Exit	Quit GEONAMICA®	2.1.8 Closing Waikato SDSS

2.5.2 Simulation menu


You use the *Simulation* menu to control the simulation. The commands *Step*, *Run*, *Stop* and *Reset* can also be invoked when pressing the respective buttons from the *Toolbar*.



Use this command	To...	Link
Init	Recalculate variables that are affected by changes in the user interface. This command will not change the simulation time	Section Init
Step	Advance the simulation with one time step	Section Step
Run	Advance the simulation till the next pause tab has been reached	Section Run
Stop	Stop a simulation run	Section Stop
Reset	Switch the simulation clock back to the Current year of simulation	Section Reset
Pauses...	Set the pauses of the simulation	Section Pauses
End year...	Set the duration of the simulation in years	Not available in this version

2.5.3 Options menu

Use the *Options* menu to personalise your workspace or to access **WAIKATO SDSS'** additional functionalities.




Use this command	To...	Link
Legend-files folder...	Select the folder in which the legend files that WAIKATO SDSS uses are located and stored.	Legend editor
Write to Excel	Establish or interrupt a link between WAIKATO SDSS and the Microsoft Excel Workbook	Section Write to Excel

Use this command	To...	Link
Log maps	Store all maps produced by the system in the form of .rst files	Section Log maps
Animation maps	Store dynamic maps produced by the system in the form of .gif animations	Section Animate maps
Toolbar	View or hide the Toolbar in the WAIKATO SDSS applications window	Section The Toolbar
Status bar	View or hide the Status bar in the WAIKATO SDSS applications window	Section The Status bar

2.5.4 Window menu


Use the *Window* menu to arrange the contents of the screen and to activate one of the opened windows.



Use this command	To...	Link
Cascade	Arrange multiple opened windows in an overlapped fashion	
Tile horizontal	Arrange multiple opened windows one above another in a non-overlapped fashion	
Tile vertical	Arrange multiple opened windows side by side in a non-overlapped fashion	
Arrange icons	Arrange the icons for minimized windows at the bottom of the screen	
List of Windows	Active the selected window on the list of opened windows	

2.5.5 Help menu

Use the *Help* menu to select the type of help that you want **WAIKATO SDSS** to display on the screen. The different commands in this menu will permit to look up information about **WAIKATO SDSS**, its commands, options, and tools.



Use this command	To...	Link
Index	Get the opening screen of the on-line help file of WAIKATO SDSS	Section Index
Using Help	Get general instructions on how to use the Windows Help system	Section Using Help
Licence...	Open the Licence window	Section Licence
About...	Open the About window	Section About

2.6 Appendix

Scaling methods

Since the classification of the values is a partition of the specified range of values, only the intermediate class boundaries need to be calculated, that is, the upper bound of a class is equal to the lower bound of the next class, assuming an ascending order. To properly define the different scales, we will first introduce some notation.

Let n be the number of classes, N the number of values in the map, min the minimum and max the maximum of the total range of the legend;

$$\text{Let } c = \begin{cases} 0 & \text{if } min > 0 \\ 1 - min & \text{else} \end{cases};$$

Let ave , sd denote the statistical average and standard deviation of all values in the map, respectively;

Let $lowerbound(i)$ denote the lower bound of class i , where the class index is zero-based and $lowerbound(0) = min$ unless otherwise specified.

Scaling method	Algorithm
Linear	$x = (max - min)/n$ $lowerbound(i) = min + i \cdot x$ for all $i \geq 1$ Each class has the same width.
Arithmetic	$x = (max - min)/(n \cdot (n + 1)/2)$ $lowerbound(i) = lowerbound(i - 1) + i \cdot x$ for all $i \geq 1$ This scale is useful for values that grow quadratic.
Geometric	$x = 10^{(\log_{10}(max+c) - \log_{10}(min+c))/n}$ $lowerbound(i) = (lowerbound(i - 1) + c) \cdot x - c$ for all $i \geq 1$ This scale is useful for values that grow exponentially.
Over-geometric	$x = 10^{(\log_{10}(max+c) - \log_{10}(min+c))/(n \cdot (n + 1)/2)}$ $lowerbound(i) = (lowerbound(i - 1) + c) \cdot x^i - c$ for all $i \geq 1$ This is an arithmetic scale of a geometric scale.
Harmonic	$x = (\frac{1}{min+c} - \frac{1}{max+c})/n$ $lowerbound(i) = 1/(\frac{1}{min+c} - i \cdot x) - c$ for all $i \geq 1$ This scale is useful for values that follow a factorial function.
Quantiles	An equal amount of values is put in every class, that is, all values in the map are stored in a vector $data$ that is sorted in ascending order. Then: $lowerbound(i) = (data(\lfloor i \cdot N/n \rfloor) + data(\lceil i \cdot N/n \rceil))/2$.
Standardised discretisation	$lowerbound(i) = ave - sd \cdot (n/2 + i - 2)$ Class bounds that exceed the specified range are cut of at the minimum and maximum of that range.

Scaling method	Algorithm
Method of Bertin	$x_{left} = 2 \cdot (ave - min) / n$ $x_{right} = 2 \cdot (max - ave) / n$ $lowerbound(i) = lowerbound(i-1) + x_{left} \quad \text{for all } 1 \leq i \leq \frac{n-1}{2}$ $lowerbound(i) = lowerbound(i-1) + (x_{left} + x_{right}) / 2 \quad \text{for } i = \frac{n+1}{2}$ <p style="text-align: center;">and n odd</p> $lowerbound(i) = lowerbound(i-1) + x_{right} \quad \text{for all } \frac{n+1}{2} \leq i < n$ <p>This scale divides the range into two linear scales around the average.</p>
Fifth-order polynomial	<p>This method fits a fifth-order polynomial f through the values in the map, using an ordinary least squares regression. The class bounds are taken as $f(data(i \cdot N/n))$, where data is a vector of the value in the map sorted in ascending order. Note that the lower bound of the first class may be less than min, due to the fitting of the polynomial.</p>

Effectiveness

Let $v(i)$ be a function of the i th value in the map;

Let $c(i)$ be the class that contains the i th value of the map;

Let $|c|$ be the number of values in class c .

The effectiveness of the classification is estimated by the following formula:

$$MSW = \frac{1}{N-n} \sum_{i=1}^N \left(v(i) - \frac{1}{|c|} \sum_{\{j|c(j)=c(i)\}} v(j) \right)^2$$

$$MST = \frac{1}{N-1} \sum_{i=1}^N \left(v(i) - \frac{1}{N} \sum_j v(j) \right)^2$$

$$effectiveness = (1 - MSW/MST) \cdot 100\%$$

MSW is the mean of the squared deviations within the class, that is, the deviation from the class average. MST is the mean of the squared deviations from the mean – the T stands for total. Put in words, the effectiveness indicates what portion of the variance in the values is accounted for by the classification. To get a fair estimate of the effectiveness, the assumed distribution of the values when calculating the deviations need to be taken into account. Therefore, the function $v()$ should be the inverse of the function that determines the class bounds. Since not all scales can be defined as continuous functions, inverse functions have been defined only for the first four scales. Let $value(i)$ denote the value of the i th element of the map.

Scaling method	Inverse function
Linear scale	$v(i) = value(i)$
Arithmetic scale	$v(i) = \begin{cases} \sqrt{value(i) - min} & \text{if } value(i) > min + c \\ 0 & \text{else} \end{cases}$
Geometric scale	$c = \max\{1 - min, 0\}$ $v(i) = \begin{cases} \log_{10}(value(i) + c) & \text{if } value(i) > 1 - c \\ 0 & \text{else} \end{cases}$
Over-geometric scale	$v(i) = \begin{cases} \sqrt{\log_{10}(value(i) + c) - \log_{10}(min + c)} & \text{if } value(i) > min + c \\ 0 & \text{else} \end{cases}$

For the other scaling methods the estimated effectiveness is taken as the maximum of the effectiveness, using the function of the linear scale and of the geometric scale.

DRAFT

3. The Integrated Model

DRAFT

4. Model building blocks

TODO

DRAFT

5. Indicators

TODO

DRAFT

References

Reference list

DRAFT

DRAFT



P.O. Box 463



6200 AL Maastricht



The Netherlands



Tel. +31 (43) 388 33 22



Fax +31 (43) 325 31 55